

Network Working Group
Request for Comments: 4750
Obsoletes: 1850
Category: Standards Track

D. Joyal, Ed.
Nortel
P. Galecki, Ed.
Airvana
S. Giacalone, Ed.
CSFB
Original Authors:
R. Coltun
Touch Acoustra
F. Baker
Cisco Systems
December 2006

OSPF Version 2 Management Information Base

Status of This Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The IETF Trust (2006).

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in TCP/IP-based internets. In particular, it defines objects for managing version 2 of the Open Shortest Path First Routing Protocol. Version 2 of the OSPF protocol is specific to the IPv4 address family. Version 3 of the OSPF protocol is specific to the IPv6 address family.

This memo obsoletes RFC 1850; however, it is designed to be backwards compatible. The functional differences between this memo and RFC 1850 are explained in Appendix B.

Table of Contents

1. Overview	3
1.1. The Internet-Standard Management Framework	3
1.2. Conceptual Row Creation	3
1.3. Default Configuration	4
1.4. OSPF Counters	5
1.5. Multiple OSPF Instances	5
1.6. Conventions	6
2. Structure of This MIB	6
2.1. The Purposes of the Sections in This MIB	6
2.1.1. General Variables	6
2.1.2. Area Data Structure and Area Stub Metric Table	6
2.1.3. Link State Database and External Link State Database	7
2.1.4. Address Table and Host Tables	7
2.1.5. Interface and Interface Metric Tables	7
2.1.6. Virtual Interface Table	7
2.1.7. Neighbor and Virtual Neighbor Tables	7
2.1.8. Local Link State Database Table and Virtual Local Link State Database Table	7
2.1.9. AS-scope Link State Database Table	7
2.1.10. Area LSA Count Table	7
3. OSPF MIB Module	8
4. OSPF Trap Overview	94
4.1. Introduction	94
4.2. Approach	95
4.3. Ignoring Initial Activity	95
4.4. Throttling Traps	95
4.5. One Trap Per OSPF Event	96
4.6. Polling Event Counters	96
4.7. Translating Notification Parameters	97
4.8. Historical Artifacts	97
5. OSPF Trap Definitions	98
6. Security Considerations	110
7. IANA Considerations	111
8. Acknowledgements	111
9. References	111
9.1. Normative References	111
9.2. Informative References	111
Appendix A. TOS Support	113
Appendix B. Changes from RFC 1850	113
B.1. General Group Changes	113
B.2. OSPF NSSA Enhancement Support	113
B.3. Opaque LSA Support	114
B.4. Graceful Restart Support	116
B.5. OSPF Compliances	116
B.6. OSPF Authentication and Security	117

B.7. OSPF Trap MIB	117
B.8. Miscellaneous	118

1. Overview

1.1. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

1.2. Conceptual Row Creation

For the benefit of row-creation in "conceptual" tables, DEFVAL (Default Value) clauses are included in the definitions in section 3, suggesting values that an agent should use for instances of variables that need to be created due to a Set-Request, but that are not specified in the Set-Request. DEFVAL clauses have not been specified for some objects that are read-only, implying that they are zeroed upon row creation. These objects are of the SYNTAX Counter32 or Gauge32.

For those objects not having a DEFVAL clause, both management stations and agents should heed the Robustness Principle of the Internet (see [RFC791]):

"be liberal in what you accept, conservative in what you send"

Therefore, management stations should include as many of these columnar objects as possible (e.g., all read-write objects) in a Set-Request when creating a conceptual row. Agents should accept a Set-Request with as few of these columnar objects as they need (e.g., the minimum contents of a "row-creating" SET consists of those objects for which, as they cannot be intuited, no default is specified).

1.3. Default Configuration

OSPF is a powerful routing protocol, equipped with features to handle virtually any configuration requirement that might reasonably be found within an Autonomous System (AS). With this power comes a fair degree of complexity, which the sheer number of objects in the MIB will attest to. Care has therefore been taken, in constructing this MIB, to define default values for virtually every object, to minimize the amount of parameterization required in the typical case. That default configuration is as follows:

Given the following assumptions:

- IP has already been configured.
- The ifTable has already been configured.
- ifSpeed is estimated by the interface drivers.
- The OSPF process automatically discovers all IP interfaces and creates corresponding OSPF interfaces.
- The OSPF process automatically creates the areas required for the interfaces.

The simplest configuration of an OSPF process requires the following:

- The OSPF process be enabled.

This can be accomplished with a single SET:

```
ospfAdminStat := enabled.
```

The configured system will have the following attributes:

- The RouterID will be one of the IP addresses of the device.
- The device will be neither an Area Border Router nor an Autonomous System Border Router.
- Every IP interface, with or without an address, will be an OSPF interface.
- The AreaID of each interface will be 0.0.0.0, the backbone.
- Authentication will be disabled.

- All broadcast and point-to-point interfaces will be operational. Non-broadcast multi-access (NBMA) interfaces require the configuration of at least one neighbor.

- Timers on all direct interfaces will be:

Hello Interval:	10 seconds
Dead Timeout:	40 Seconds
Retransmission:	5 Seconds
Transit Delay:	1 Second
Poll Interval:	120 Seconds

- No direct links to hosts will be configured.

- No addresses will be summarized.

- Metrics, being a measure of bit duration, are unambiguous and intelligent.

- No virtual links will be configured.

1.4. OSPF Counters

This MIB defines several counters, namely:

- ospfOriginateNewLsas, ospfRxNewLsas in the ospfGeneralGroup
- ospfSpfRuns, ospfAreaNssaTranslatorEvents in the ospfAreaTable
- ospfIfEvents in the ospfIfTable
- ospfVirtIfEvents in the ospfVirtIfTable
- ospfNbrEvents in the ospfNbrTable
- ospfVirtNbrEvents in the ospfVirtNbrTable

As a best practice, a management entity, when reading these counters, should use the discontinuity object, ospfDiscontinuityTime, to determine if an event that would invalidate the management entity understanding of the counters has occurred. A restart of the OSPF routing process is a possible example of a discontinuity event.

1.5. Multiple OSPF Instances

SNMPv3 supports "Contexts" that can be used to implement MIB views on multiple OSPF instances on the same system. See [RFC3411] or its successors for details.

1.6. Conventions

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119 [RFC2119].

2. Structure of This MIB

This MIB is composed of the following sections:

- General Variables
- Area Data Structure
- Area Stub Metric Table
- Link State Database (LSDB)
- Address Range Table
- Host Table
- Interface Table
- Interface Metric Table
- Virtual Interface Table
- Neighbor Table
- Virtual Neighbor Table
- External Link State Database
- Aggregate Range Table
- Local Link State Database
- AS-scope Link State Database

It supports the base OSPFv2 specification [RFC2328] and extensions to OSPFv2 such as [RFC1765], [RFC1793], [RFC2370], [RFC3101] and [RFC3623].

There exists a separate MIB for notifications ("traps"), which is entirely optional.

2.1. The Purposes of the Sections in This MIB

2.1.1. General Variables

The general variables describe (as it may seem from the name) variables that are global to the OSPF Process.

2.1.2. Area Data Structure and Area Stub Metric Table

The Area Data Structure describes all of the OSPF Areas that the router participates in. The Area Table includes data for Not-So-Stubby-Area (NSSA) translation.

The Area Stub Metric Table describes the metrics advertised into a stub area by the default router(s).

2.1.3. Link State Database and External Link State Database

The link state database is provided primarily to provide detailed information for network debugging.

2.1.4. Address Table and Host Tables

The Address Range Table and Host Table are provided to view configured Network Summary and host route information.

2.1.5. Interface and Interface Metric Tables

The Interface Table and the Interface Metric Table together describe the various IP interfaces to OSPF. The metrics are placed in separate tables in order to simplify dealing with multiple types of service. The Interface table includes link-local (Opaque type-9) link state advertisement (LSA) statistics.

2.1.6. Virtual Interface Table

The Virtual Interface Table describes virtual links to the OSPF Process, similarly to the (non-virtual) Interface Tables. This Table includes link-local (Opaque type-9) LSA statistics.

2.1.7. Neighbor and Virtual Neighbor Tables

The Neighbor Table and the Virtual Neighbor Table describe the neighbors to the OSPF Process.

2.1.8. Local Link State Database Table and Virtual Local Link State Database Table

The Local Link State Database Table and Virtual Local Link State Database Table are identical to the OSPF LSDB Table in format, but contain only link-local (Opaque type-9) link state advertisements for non-virtual and virtual links.

2.1.9. AS-scope Link State Database Table

The AS-scope Link State Database Table is identical to the OSPF LSDB Table in format, but contains only AS-scoped link state advertisements.

2.1.10. Area LSA Count Table

The table, which maintains number of link state advertisements on the per-area, per-LSA-type basis.

3. OSPF MIB Module

```
OSPF-MIB DEFINITIONS ::= BEGIN
```

```
IMPORTS
```

```
    MODULE-IDENTITY, OBJECT-TYPE, Counter32, Gauge32,  
    Integer32, Unsigned32, IpAddress, mib-2  
        FROM SNMPv2-SMI  
    TEXTUAL-CONVENTION, TruthValue, RowStatus, TimeStamp  
        FROM SNMPv2-TC  
    MODULE-COMPLIANCE, OBJECT-GROUP  
        FROM SNMPv2-CONF  
    InterfaceIndexOrZero  
        FROM IF-MIB;
```

```
ospf MODULE-IDENTITY
```

```
    LAST-UPDATED "200611100000Z" -- November 10, 2006 00:00:00 EST  
    ORGANIZATION "IETF OSPF Working Group"  
    CONTACT-INFO  
        "WG E-Mail: ospf@ietf.org"
```

```
        WG Chairs: acee@cisco.com  
                    rohit@gmail.com
```

```
        Editors: Dan Joyal  
                  Nortel  
                  600 Technology Park Drive  
                  Billerica, MA 01821  
                  djoyal@nortel.com
```

```
        Piotr Galecki  
        Airvana  
        19 Alpha Road  
        Chelmsford, MA 01824  
        pgalecki@airvana.com
```

```
        Spencer Giacalone  
        CSFB  
        Eleven Madison Ave  
        New York, NY 10010-3629  
        spencer.giacalone@gmail.com"
```

```
DESCRIPTION
```

```
"The MIB module to describe the OSPF Version 2  
Protocol. Note that some objects in this MIB  
module may pose a significant security risk.  
Refer to the Security Considerations section  
in RFC 4750 for more information.
```

Copyright (C) The IETF Trust (2006).
This version of this MIB module is part of
RFC 4750; see the RFC itself for full legal
notices."

REVISION "200611100000Z" -- November 10, 2006 09:00:00 EST
DESCRIPTION

"Updated for latest changes to OSPF Version 2:
- updated the General Group with the new
ospfRFC1583Compatibility, ospfReferenceBandwidth
and ospfDiscontinuityTime objects
- added graceful-restart-related objects
- added stub-router-related objects
- updated the Area Table with NSSA-related objects
- added ospfAreaAggregateExtRouteTag object
- added Opaque LSA-related objects
- updates to the Compliances and Security sections
- added area LSA counter table
- added section describing translation of notification
parameters between SNMP versions
- added ospfComplianceObsolete to contain obsolete
object groups
- deprecated ospfExtLsdbTable
See Appendix B of RFC 4750 for more details.

This version published as part of RFC 4750"

REVISION "199501201225Z" -- Fri Jan 20 12:25:50 PST 1995

DESCRIPTION

"The initial SMIv2 revision of this MIB module, published
in RFC 1850."
::= { mib-2 14 }

AreaID ::= TEXTUAL-CONVENTION

STATUS current

DESCRIPTION

"An OSPF Area Identifier.
Note that the Area ID, in OSPF, has the same format
as an IP address, but has the function of defining
a summarization point for link state advertisements."

SYNTAXIpAddress

RouterID ::= TEXTUAL-CONVENTION

STATUS current

DESCRIPTION

"A OSPF Router Identifier.
Note that the Router ID, in OSPF, has the same format
as an IP address, but identifies the router independent

```
        of its IP address."
SYNTAX          IpAddress

Metric ::= TEXTUAL-CONVENTION
DISPLAY-HINT "d-0"
STATUS         current
DESCRIPTION
    "The OSPF internal metric.
     Note that the OSPF metric is defined as an unsigned value
     in the range."
SYNTAX          Integer32 (0..'FFFF'h)

BigMetric ::= TEXTUAL-CONVENTION
DISPLAY-HINT "d-0"
STATUS         current
DESCRIPTION
    "The OSPF external metric."
SYNTAX          Integer32 (0..'FFFFFF'h)

Status ::= TEXTUAL-CONVENTION
STATUS         current
DESCRIPTION
    "An indication of the operability of an OSPF
     function or feature. For example, the status
     of an interface: 'enabled' indicates that
     it is willing to communicate with other OSPF routers,
     and 'disabled' indicates that it is not."
SYNTAX          INTEGER { enabled (1), disabled (2) }

PositiveInteger ::= TEXTUAL-CONVENTION
DISPLAY-HINT "d-0"
STATUS         current
DESCRIPTION
    "A positive integer. Values in excess are precluded as
     unnecessary and prone to interoperability issues."
SYNTAX          Integer32 (0..'7FFFFFFF'h)

HelloRange ::= TEXTUAL-CONVENTION
DISPLAY-HINT "d-0"
STATUS         current
DESCRIPTION
    "The range of intervals in seconds on which Hello messages
     are exchanged."
SYNTAX          Integer32 (1..'FFFF'h)

UpToMaxAge ::= TEXTUAL-CONVENTION
DISPLAY-HINT "d-0"
STATUS         current
```

DESCRIPTION

"The values in seconds that one might find or configure for variables bounded by the maximum age of an LSA."

SYNTAX Integer32 (0..3600)

DesignatedRouterPriority ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d-0"

STATUS current

DESCRIPTION

"The range of values defined for the priority of a system for becoming the designated router."

SYNTAX Integer32 (0..'FF'h)

TOSType ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d-0"

STATUS current

DESCRIPTION

"Type of Service (TOS) is defined as a mapping to the IP Type of Service Flags as defined in the IP Forwarding Table MIB

PRECEDENCE	TYPE OF SERVICE	0

IP TOS		IP TOS	
Field	Policy	Field	Policy
Contents	Code	Contents	Code
0 0 0 0	=> 0	0 0 0 1	=> 2
0 0 1 0	=> 4	0 0 1 1	=> 6
0 1 0 0	=> 8	0 1 0 1	=> 10
0 1 1 0	=> 12	0 1 1 1	=> 14
1 0 0 0	=> 16	1 0 0 1	=> 18
1 0 1 0	=> 20	1 0 1 1	=> 22
1 1 0 0	=> 24	1 1 0 1	=> 26
1 1 1 0	=> 28	1 1 1 1	=> 30

The remaining values are left for future definition."

SYNTAX Integer32 (0..30)

OspfAuthenticationType ::= TEXTUAL-CONVENTION

STATUS current

DESCRIPTION

"The authentication type."

SYNTAX INTEGER {

```

        none (0),
        simplePassword (1),
        md5 (2)
        -- reserved for specification by IANA (> 2)
    }

-- OSPF General Variables

-- Note: These parameters apply globally to the Router's
-- OSPF Process.

ospfGeneralGroup OBJECT IDENTIFIER ::= { ospf 1 }

ospfRouterId OBJECT-TYPE
    SYNTAX      RouterID
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "A 32-bit integer uniquely identifying the
        router in the Autonomous System.
        By convention, to ensure uniqueness, this
        should default to the value of one of the
        router's IP interface addresses.

        This object is persistent and when written
        the entity SHOULD save the change to non-volatile storage."
    REFERENCE
        "OSPF Version 2, C.1 Global parameters"
    ::= { ospfGeneralGroup 1 }

ospfAdminStat OBJECT-TYPE
    SYNTAX      Status
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "The administrative status of OSPF in the
        router. The value 'enabled' denotes that the
        OSPF Process is active on at least one interface;
        'disabled' disables it on all interfaces.

        This object is persistent and when written
        the entity SHOULD save the change to non-volatile storage."
    ::= { ospfGeneralGroup 2 }

ospfVersionNumber OBJECT-TYPE
    SYNTAX      INTEGER { version2 (2) }
    MAX-ACCESS  read-only
    STATUS      current

```

DESCRIPTION

"The current version number of the OSPF protocol is 2."

REFERENCE

"OSPF Version 2, Title"
 ::= { ospfGeneralGroup 3 }

ospfAreaBdrRtrStatus OBJECT-TYPE

SYNTAX TruthValue
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"A flag to note whether this router is an Area Border Router."

REFERENCE

"OSPF Version 2, Section 3 Splitting the AS into Areas"
 ::= { ospfGeneralGroup 4 }

ospfASBdrRtrStatus OBJECT-TYPE

SYNTAX TruthValue
MAX-ACCESS read-write
STATUS current

DESCRIPTION

"A flag to note whether this router is configured as an Autonomous System Border Router.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

REFERENCE

"OSPF Version 2, Section 3.3 Classification of routers"
 ::= { ospfGeneralGroup 5 }

ospfExternLsaCount OBJECT-TYPE

SYNTAX Gauge32
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"The number of external (LS type-5) link state advertisements in the link state database."

REFERENCE

"OSPF Version 2, Appendix A.4.5 AS external link advertisements"
 ::= { ospfGeneralGroup 6 }

ospfExternLsaCksumSum OBJECT-TYPE

SYNTAX Integer32
MAX-ACCESS read-only

STATUS current
DESCRIPTION
 "The 32-bit sum of the LS checksums of the external link state advertisements contained in the link state database. This sum can be used to determine if there has been a change in a router's link state database and to compare the link state database of two routers. The value should be treated as unsigned when comparing two sums of checksums."
 ::= { ospfGeneralGroup 7 }

ospfTOSSupport OBJECT-TYPE
 SYNTAX TruthValue
 MAX-ACCESS read-write
 STATUS current
DESCRIPTION
 "The router's support for type-of-service routing.
 This object is persistent and when written the entity SHOULD save the change to non-volatile storage."
REFERENCE
 "OSPF Version 2, Appendix F.1.2 Optional TOS support"
 ::= { ospfGeneralGroup 8 }

ospfOriginateNewLsas OBJECT-TYPE
 SYNTAX Counter32
 MAX-ACCESS read-only
 STATUS current
DESCRIPTION
 "The number of new link state advertisements that have been originated. This number is incremented each time the router originates a new LSA.
 Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of ospfDiscontinuityTime."
 ::= { ospfGeneralGroup 9 }

ospfRxNewLsas OBJECT-TYPE
 SYNTAX Counter32
 MAX-ACCESS read-only
 STATUS current
DESCRIPTION

"The number of link state advertisements received that are determined to be new instantiations. This number does not include newer instantiations of self-originated link state advertisements.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of ospfDiscontinuityTime."

::= { ospfGeneralGroup 10 }

ospfExtLsdbLimit OBJECT-TYPE
SYNTAX Integer32 (-1..'7FFFFFFF'h)
MAX-ACCESS read-write
STATUS current
DESCRIPTION
 "The maximum number of non-default AS-external LSAs entries that can be stored in the link state database. If the value is -1, then there is no limit.

When the number of non-default AS-external LSAs in a router's link state database reaches **ospfExtLsdbLimit**, the router enters overflow state. The router never holds more than **ospfExtLsdbLimit** non-default AS-external LSAs in its database. **OspfExtLsdbLimit** MUST be set identically in all routers attached to the OSPF backbone and/or any regular OSPF area (i.e., OSPF stub areas and NSSAs are excluded).

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

DEFVAL { -1 }
 ::= { ospfGeneralGroup 11 }

ospfMulticastExtensions OBJECT-TYPE
SYNTAX Integer32
MAX-ACCESS read-write
STATUS current
DESCRIPTION
 "A bit mask indicating whether the router is forwarding IP multicast (Class D) datagrams based on the algorithms defined in the multicast extensions to OSPF.

Bit 0, if set, indicates that the router can

forward IP multicast datagrams in the router's directly attached areas (called intra-area multicast routing).

Bit 1, if set, indicates that the router can forward IP multicast datagrams between OSPF areas (called inter-area multicast routing).

Bit 2, if set, indicates that the router can forward IP multicast datagrams between Autonomous Systems (called inter-AS multicast routing).

Only certain combinations of bit settings are allowed, namely: 0 (no multicast forwarding is enabled), 1 (intra-area multicasting only), 3 (intra-area and inter-area multicasting), 5 (intra-area and inter-AS multicasting), and 7 (multicasting everywhere). By default, no multicast forwarding is enabled.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

```
DEFVAL { 0 }
 ::= { ospfGeneralGroup 12 }
```

ospfExitOverflowInterval OBJECT-TYPE

SYNTAX PositiveInteger

MAX-ACCESS read-write

STATUS current

DESCRIPTION

"The number of seconds that, after entering OverflowState, a router will attempt to leave OverflowState. This allows the router to again originate non-default AS-external LSAs. When set to 0, the router will not leave overflow state until restarted.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

```
DEFVAL { 0 }
 ::= { ospfGeneralGroup 13 }
```

ospfDemandExtensions OBJECT-TYPE

SYNTAX TruthValue

MAX-ACCESS read-write

```
STATUS      current
DESCRIPTION
  "The router's support for demand routing.
  This object is persistent and when written
  the entity SHOULD save the change to non-volatile
  storage."
REFERENCE
  "Extending OSPF to Support Demand Circuits"
  ::= { ospfGeneralGroup 14 }

ospfRFC1583Compatibility OBJECT-TYPE
  SYNTAX      TruthValue
  MAX-ACCESS  read-write
  STATUS      current
  DESCRIPTION
    "Indicates metrics used to choose among multiple
    AS-external LSAs. When RFC1583Compatibility is set to
    enabled, only cost will be used when choosing among
    multiple AS-external LSAs advertising the same
    destination. When RFC1583Compatibility is set to
    disabled, preference will be driven first by type of
    path using cost only to break ties.

    This object is persistent and when written
    the entity SHOULD save the change to non-volatile
    storage."
  REFERENCE
    "OSPF Version 2, Section 16.4.1 External path
     preferences"
  ::= { ospfGeneralGroup 15 }

ospfOpaqueLsaSupport OBJECT-TYPE
  SYNTAX      TruthValue
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "The router's support for Opaque LSA types."
  REFERENCE
    "The OSPF Opaque LSA Option"
  ::= { ospfGeneralGroup 16 }

ospfReferenceBandwidth OBJECT-TYPE
  SYNTAX      Unsigned32
  UNITS      "kilobits per second"
  MAX-ACCESS  read-write
  STATUS      current
  DESCRIPTION
    "Reference bandwidth in kilobits/second for
```

calculating default interface metrics. The default value is 100,000 KBPS (100 MBPS).

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

```
::= { ospfGeneralGroup 17 }
```

ospfRestartSupport OBJECT-TYPE

SYNTAX INTEGER { none (1),
 plannedOnly (2),
 plannedAndUnplanned (3)
 }

MAX-ACCESS read-write

STATUS current

DESCRIPTION

"The router's support for OSPF graceful restart. Options include: no restart support, only planned restarts, or both planned and unplanned restarts.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

```
::= { ospfGeneralGroup 18 }
```

ospfRestartInterval OBJECT-TYPE

SYNTAX Integer32 (1..1800)

UNITS "seconds"

MAX-ACCESS read-write

STATUS current

DESCRIPTION

"Configured OSPF graceful restart timeout interval.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

```
::= { ospfGeneralGroup 19 }
```

ospfRestartStrictLsaChecking OBJECT-TYPE

SYNTAX TruthValue

MAX-ACCESS read-write

STATUS current

DESCRIPTION

"Indicates if strict LSA checking is enabled for graceful restart.

This object is persistent and when written the entity SHOULD save the change to non-volatile

```

storage."
 ::= { ospfGeneralGroup 20 }

ospfRestartStatus OBJECT-TYPE
    SYNTAX      INTEGER { notRestarting (1),
                      plannedRestart (2),
                      unplannedRestart (3)
                    }
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Current status of OSPF graceful restart."
    ::= { ospfGeneralGroup 21 }

ospfRestartAge OBJECT-TYPE
    SYNTAX      Unsigned32
    UNITS       "seconds"
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Remaining time in current OSPF graceful restart
         interval."
    ::= { ospfGeneralGroup 22 }

ospfRestartExitReason OBJECT-TYPE
    SYNTAX      INTEGER { none (1),          -- none attempted
                        inProgress (2),     -- restart in
                        completed (3),      -- progress
                        successfully (4),   -- successfully
                        completed (5)       -- completed
                        timedOut (4),       -- timed out
                        topologyChanged (5) -- aborted due to
                                              -- topology change.
                      }
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Describes the outcome of the last attempt at a
         graceful restart. If the value is 'none', no restart
         has yet been attempted. If the value is 'inProgress',
         a restart attempt is currently underway."
    ::= { ospfGeneralGroup 23 }

ospfAsLsaCount OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current

```

DESCRIPTION

"The number of AS-scope link state advertisements in the AS-scope link state database."
 ::= { ospfGeneralGroup 24 }

ospfAsLsaCksumSum OBJECT-TYPE

SYNTAX Unsigned32
 MAX-ACCESS read-only
 STATUS current

DESCRIPTION

"The 32-bit unsigned sum of the LS checksums of the AS link state advertisements contained in the AS-scope link state database. This sum can be used to determine if there has been a change in a router's AS-scope link state database, and to compare the AS-scope link state database of two routers."

::= { ospfGeneralGroup 25 }

ospfStubRouterSupport OBJECT-TYPE

SYNTAX TruthValue
 MAX-ACCESS read-only
 STATUS current

DESCRIPTION

"The router's support for stub router functionality."

REFERENCE

"OSPF Stub Router Advertisement"

::= { ospfGeneralGroup 26 }

ospfStubRouterAdvertisement OBJECT-TYPE

SYNTAX INTEGER {
 doNotAdvertise (1),
 advertise(2)
 }

MAX-ACCESS read-write
 STATUS current

DESCRIPTION

"This object controls the advertisement of stub router LSAs by the router. The value doNotAdvertise will result in the advertisement of a standard router LSA and is the default value.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

::= { ospfGeneralGroup 27 }

ospfDiscontinuityTime OBJECT-TYPE

SYNTAX TimeStamp

```

MAX-ACCESS read-only
STATUS current
DESCRIPTION
"The value of sysUpTime on the most recent occasion
at which any one of this MIB's counters suffered
a discontinuity.

If no such discontinuities have occurred since the last
re-initialization of the local management subsystem,
then this object contains a zero value."
 ::= { ospfGeneralGroup 28 }

-- OSPF Area Table
-- The OSPF Area Table contains information
-- regarding the various areas.

ospfAreaTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfAreaEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Information describing the configured parameters and
        cumulative statistics of the router's attached areas.
        The interfaces and virtual links are configured
        as part of these areas.  Area 0.0.0.0, by definition,
        is the backbone area."
    REFERENCE
        "OSPF Version 2, Section 6 The Area Data Structure"
    ::= { ospf 2 }

ospfAreaEntry OBJECT-TYPE
    SYNTAX      OspfAreaEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Information describing the configured parameters and
        cumulative statistics of one of the router's attached areas.
        The interfaces and virtual links are configured as part of
        these areas.  Area 0.0.0.0, by definition, is the backbone
        area.

        Information in this table is persistent and when this object
        is written the entity SHOULD save the change to non-volatile
        storage."
    INDEX { ospfAreaId }
    ::= { ospfAreaTable 1 }

```

```

OspfAreaEntry ::= 
SEQUENCE {
    ospfAreaId
        AreaID,
    ospfAuthType
        OspfAuthenticationType,
    ospfImportAsExtern
        INTEGER,
    ospfSpfRuns
        Counter32,
    ospfAreaBdrRtrCount
        Gauge32,
    ospfAsBdrRtrCount
        Gauge32,
    ospfAreaLsaCount
        Gauge32,
    ospfAreaLsaCksumSum
        Integer32,
    ospfAreaSummary
        INTEGER,
    ospfAreaStatus
        RowStatus,
    ospfAreaNssaTranslatorRole
        INTEGER,
    ospfAreaNssaTranslatorState
        INTEGER,
    ospfAreaNssaTranslatorStabilityInterval
        PositiveInteger,
    ospfAreaNssaTranslatorEvents
        Counter32
}

ospfAreaId OBJECT-TYPE
    SYNTAX      AreaID
    MAX-ACCESS  read-only -- read-only since originally
                  -- an SMIv1 index
    STATUS      current
    DESCRIPTION
        "A 32-bit integer uniquely identifying an area.
         Area ID 0.0.0.0 is used for the OSPF backbone."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
    ::= { ospfAreaEntry 1 }

ospfAuthType OBJECT-TYPE
    SYNTAX      OspfAuthenticationType
    MAX-ACCESS  read-create
    STATUS      obsolete

```

DESCRIPTION

"The authentication type specified for an area."

REFERENCE

"OSPF Version 2, Appendix D Authentication"

DEFVAL { none } -- no authentication, by default
::= { ospfAreaEntry 2 }

ospfImportAsExtern OBJECT-TYPE

SYNTAX INTEGER {
 importExternal (1),
 importNoExternal (2),
 importNssa (3)
 }

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"Indicates if an area is a stub area, NSSA, or standard area. Type-5 AS-external LSAs and type-11 Opaque LSAs are not imported into stub areas or NSSAs. NSSAs import AS-external data as type-7 LSAs"

REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"

DEFVAL { importExternal }
::= { ospfAreaEntry 3 }

ospfSpfRuns OBJECT-TYPE

SYNTAX Counter32
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"The number of times that the intra-area route table has been calculated using this area's link state database. This is typically done using Dijkstra's algorithm.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of **ospfDiscontinuityTime**."

::= { ospfAreaEntry 4 }

ospfAreaBdrRtrCount OBJECT-TYPE

SYNTAX Gauge32
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"The total number of Area Border Routers reachable within this area. This is initially zero and is calculated in each Shortest Path First (SPF) pass."

```

 ::= { ospfAreaEntry 5 }

ospfAsBdrRtrCount OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The total number of Autonomous System Border
         Routers reachable within this area. This is
         initially zero and is calculated in each SPF
         pass."
 ::= { ospfAreaEntry 6 }

ospfAreaLsaCount OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The total number of link state advertisements
         in this area's link state database, excluding
         AS-external LSAs."
 ::= { ospfAreaEntry 7 }

ospfAreaLsaCksumSum OBJECT-TYPE
    SYNTAX      Integer32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The 32-bit sum of the link state
         advertisements' LS checksums contained in this
         area's link state database. This sum excludes
         external (LS type-5) link state advertisements.
         The sum can be used to determine if there has
         been a change in a router's link state
         database, and to compare the link state database of
         two routers. The value should be treated as unsigned
         when comparing two sums of checksums."
    DEFVAL { 0 }
 ::= { ospfAreaEntry 8 }

ospfAreaSummary OBJECT-TYPE
    SYNTAX      INTEGER {
                  noAreaSummary (1),
                  sendAreaSummary (2)
                }
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION

```

"The variable ospfAreaSummary controls the import of summary LSAs into stub and NSSA areas. It has no effect on other areas.

If it is noAreaSummary, the router will not originate summary LSAs into the stub or NSSA area. It will rely entirely on its default route.

If it is sendAreaSummary, the router will both summarize and propagate summary LSAs."

```
DEFVAL { noAreaSummary }
 ::= { ospfAreaEntry 9 }
```

ospfAreaStatus OBJECT-TYPE
 SYNTAX RowStatus
 MAX-ACCESS read-create
 STATUS current
 DESCRIPTION
 "This object permits management of the table by facilitating actions such as row creation, construction, and destruction.

The value of this object has no effect on whether other objects in this conceptual row can be modified."

```
::= { ospfAreaEntry 10 }
```

ospfAreaNssaTranslatorRole OBJECT-TYPE
 SYNTAX INTEGER { always (1), candidate (2) }
 MAX-ACCESS read-create
 STATUS current
 DESCRIPTION
 "Indicates an NSSA border router's ability to perform NSSA translation of type-7 LSAs into type-5 LSAs."
 DEFVAL { candidate }
 ::= { ospfAreaEntry 11 }

ospfAreaNssaTranslatorState OBJECT-TYPE
 SYNTAX INTEGER { enabled (1),
 elected (2),
 disabled (3)
 }
 MAX-ACCESS read-only
 STATUS current
 DESCRIPTION
 "Indicates if and how an NSSA border router is performing NSSA translation of type-7 LSAs into type-5

LSAs. When this object is set to enabled, the NSSA Border router's OspfAreaNssaExtTranslatorRole has been set to always. When this object is set to elected, a candidate NSSA Border router is Translating type-7 LSAs into type-5. When this object is set to disabled, a candidate NSSA border router is NOT translating type-7 LSAs into type-5."

```
::= { ospfAreaEntry 12 }
```

ospfAreaNssaTranslatorStabilityInterval OBJECT-TYPE
 SYNTAX PositiveInteger
 UNITS "seconds"
 MAX-ACCESS read-create
 STATUS current
 DESCRIPTION
 "The number of seconds after an elected translator determines its services are no longer required, that it should continue to perform its translation duties."
 DEFVAL { 40 }

```
::= { ospfAreaEntry 13 }
```

ospfAreaNssaTranslatorEvents OBJECT-TYPE
 SYNTAX Counter32
 MAX-ACCESS read-only
 STATUS current
 DESCRIPTION
 "Indicates the number of translator state changes that have occurred since the last boot-up.

 Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of ospfDiscontinuityTime."

```
::= { ospfAreaEntry 14 }
```

-- OSPF Area Default Metric Table

ospfStubAreaTable OBJECT-TYPE
 SYNTAX SEQUENCE OF OspfStubAreaEntry
 MAX-ACCESS not-accessible
 STATUS current
 DESCRIPTION
 "The set of metrics that will be advertised by a default Area Border Router into a stub area."
 REFERENCE
 "OSPF Version 2, Appendix C.2, Area Parameters"

```
::= { ospf 3 }
```

ospfStubAreaEntry OBJECT-TYPE
 SYNTAX OspfStubAreaEntry

MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
"The metric for a given Type of Service that
will be advertised by a default Area Border
Router into a stub area.

Information in this table is persistent and when this object
is written the entity SHOULD save the change to non-volatile
storage."

REFERENCE
"OSPF Version 2, Appendix C.2, Area Parameters"
INDEX { ospfStubAreaId, ospfStubTOS }
 ::= { ospfStubAreaTable 1 }

OspfStubAreaEntry ::=
SEQUENCE {
ospfStubAreaId
 AreaID,
ospfStubTOS
 TOSType,
ospfStubMetric
 BigMetric,
ospfStubStatus
 RowStatus,
ospfStubMetricType
 INTEGER
}

ospfStubAreaId OBJECT-TYPE
SYNTAX AreaID
MAX-ACCESS read-only -- read-only since originally an
-- SMIV1 index
STATUS current
DESCRIPTION
"The 32-bit identifier for the stub area. On
creation, this can be derived from the
instance."
 ::= { ospfStubAreaEntry 1 }

ospfStubTOS OBJECT-TYPE
SYNTAX TOSType
MAX-ACCESS read-only -- read-only since originally an
-- SMIV1 index
STATUS current
DESCRIPTION
"The Type of Service associated with the
metric. On creation, this can be derived from

```

    the instance."
 ::= { ospfStubAreaEntry 2 }

ospfStubMetric OBJECT-TYPE
    SYNTAX      BigMetric
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "The metric value applied at the indicated Type
         of Service. By default, this equals the least
         metric at the Type of Service among the
         interfaces to other areas."
 ::= { ospfStubAreaEntry 3 }

ospfStubStatus OBJECT-TYPE
    SYNTAX      RowStatus
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "This object permits management of the table by
         facilitating actions such as row creation,
         construction, and destruction.

        The value of this object has no effect on
        whether other objects in this conceptual row can be
        modified."
 ::= { ospfStubAreaEntry 4 }

ospfStubMetricType OBJECT-TYPE
    SYNTAX      INTEGER {
                  ospfMetric (1), -- OSPF Metric
                  comparableCost (2), -- external type 1
                  nonComparable (3) -- external type 2
                }
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "This variable displays the type of metric
         advertised as a default route."
    DEFVAL { ospfMetric }
 ::= { ospfStubAreaEntry 5 }

-- OSPF Link State Database

ospfLsdbTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfLsdbEntry
    MAX-ACCESS  not-accessible
    STATUS      current

```

DESCRIPTION

"The OSPF Process's link state database (LSDB).
The LSDB contains the link state advertisements
from throughout the areas that the device is attached to."

REFERENCE

"OSPF Version 2, Section 12 Link State Advertisements"
 ::= { ospf 4 }

ospfLsdbEntry OBJECT-TYPE

SYNTAX OspfLsdbEntry
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
"A single link state advertisement."
INDEX { ospfLsdbAreaId, ospfLsdbType,
ospfLsdbLsid, ospfLsdbRouterId }
 ::= { ospfLsdbTable 1 }

OspfLsdbEntry ::=

SEQUENCE {
ospfLsdbAreaId
 AreaID,
ospfLsdbType
 INTEGER,
ospfLsdbLsid
 IpAddress,
ospfLsdbRouterId
 RouterID,
ospfLsdbSequence
 Integer32,
ospfLsdbAge
 Integer32,
ospfLsdbChecksum
 Integer32,
ospfLsdbAdvertisement
 OCTET STRING
}

ospfLsdbAreaId OBJECT-TYPE

SYNTAX AreaID
MAX-ACCESS read-only -- read-only since originally an
-- SMIV1 index
STATUS current
DESCRIPTION
"The 32-bit identifier of the area from which
the LSA was received."
REFERENCE
"OSPF Version 2, Appendix C.2 Area parameters"

```
::= { ospfLsdbEntry 1 }
```

```
ospfLsdbType OBJECT-TYPE
    SYNTAX      INTEGER {
        routerLink (1),
        networkLink (2),
        summaryLink (3),
        asSummaryLink (4),
        asExternalLink (5), -- but see ospfAsLsdbTable
        multicastLink (6),
        nssaExternalLink (7),
        areaOpaqueLink (10)
    }
    MAX-ACCESS  read-only -- read-only since originally an
                      -- SMIv1 index
```

```
STATUS      current
```

```
DESCRIPTION
```

"The type of the link state advertisement.
Each link state type has a separate advertisement
format.

Note: External link state advertisements are permitted
for backward compatibility, but should be displayed
in the ospfAsLsdbTable rather than here."

```
REFERENCE
```

"OSPF Version 2, Appendix A.4.1 The Link State
Advertisement header"

```
::= { ospfLsdbEntry 2 }
```

```
ospfLsdbLsid OBJECT-TYPE
```

```
    SYNTAX      IpAddress
    MAX-ACCESS  read-only -- read-only since originally an
                      -- SMIv1 index
```

```
STATUS      current
```

```
DESCRIPTION
```

"The Link State ID is an LS Type Specific field
containing either a Router ID or an IP address;
it identifies the piece of the routing domain
that is being described by the advertisement."

```
REFERENCE
```

"OSPF Version 2, Section 12.1.4 Link State ID"

```
::= { ospfLsdbEntry 3 }
```

```
ospfLsdbRouterId OBJECT-TYPE
```

```
    SYNTAX      RouterID
    MAX-ACCESS  read-only -- read-only since originally an
                      -- SMIv1 index
```

```
STATUS      current
```

DESCRIPTION

"The 32-bit number that uniquely identifies the originating router in the Autonomous System."

REFERENCE

"OSPF Version 2, Appendix C.1 Global parameters"
 $::= \{ \text{ospfLsdbEntry} \ 4 \}$

ospfLsdbSequence OBJECT-TYPE

SYNTAX Integer32
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"The sequence number field is a signed 32-bit integer. It starts with the value '80000001'h, or -'7FFFFFFF'h, and increments until '7FFFFFFF'h. Thus, a typical sequence number will be very negative. It is used to detect old and duplicate Link State Advertisements. The space of sequence numbers is linearly ordered. The larger the sequence number, the more recent the advertisement."

REFERENCE

"OSPF Version 2, Section 12.1.6 LS sequence number"
 $::= \{ \text{ospfLsdbEntry} \ 5 \}$

ospfLsdbAge OBJECT-TYPE

SYNTAX Integer32 -- Should be 0..MaxAge, except when
-- doNotAge bit is set
UNITS "seconds"
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"This field is the age of the link state advertisement in seconds."

REFERENCE

"OSPF Version 2, Section 12.1.1 LS age"
 $::= \{ \text{ospfLsdbEntry} \ 6 \}$

ospfLsdbChecksum OBJECT-TYPE

SYNTAX Integer32
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"This field is the checksum of the complete contents of the advertisement, excepting the age field. The age field is excepted so that an advertisement's age can be incremented without updating the checksum. The checksum used is the same that is used for ISO connectionless

datagrams; it is commonly referred to as the Fletcher checksum."

REFERENCE

"OSPF Version 2, Section 12.1.7 LS checksum"
 $::= \{ \text{ospfLsdbEntry} \ 7 \}$

ospfLsdbAdvertisement OBJECT-TYPE

SYNTAX OCTET STRING (SIZE (1..65535))
 MAX-ACCESS read-only
 STATUS current

DESCRIPTION

"The entire link state advertisement, including its header.

Note that for variable length LSAs, SNMP agents may not be able to return the largest string size."

REFERENCE

"OSPF Version 2, Section 12 Link State Advertisements"
 $::= \{ \text{ospfLsdbEntry} \ 8 \}$

-- Address Range Table

ospfAreaRangeTable OBJECT-TYPE

SYNTAX SEQUENCE OF OspfAreaRangeEntry
 MAX-ACCESS not-accessible
 STATUS obsolete

DESCRIPTION

"The Address Range Table acts as an adjunct to the Area Table. It describes those Address Range Summaries that are configured to be propagated from an Area to reduce the amount of information about it that is known beyond its borders. It contains a set of IP address ranges specified by an IP address/IP network mask pair.
 For example, class B address range of X.X.X.X with a network mask of 255.255.0.0 includes all IP addresses from X.X.0.0 to X.X.255.255.

Note that this table is obsoleted and is replaced by the Area Aggregate Table."

REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"
 $::= \{ \text{ospf} \ 5 \}$

ospfAreaRangeEntry OBJECT-TYPE

SYNTAX OspfAreaRangeEntry
 MAX-ACCESS not-accessible
 STATUS obsolete

DESCRIPTION

"A single area address range.

Information in this table is persistent and when this object is written the entity SHOULD save the change to non-volatile storage."

REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"

INDEX { ospfAreaRangeAreaId, ospfAreaRangeNet }

::= { ospfAreaRangeTable 1 }

OspfAreaRangeEntry ::=

SEQUENCE {

- ospfAreaRangeAreaId**
- AreaID,**
- ospfAreaRangeNet**
- IpAddress,**
- ospfAreaRangeMask**
- IpAddress,**
- ospfAreaRangeStatus**
- RowStatus,**
- ospfAreaRangeEffect**
- INTEGER**

}

ospfAreaRangeAreaId OBJECT-TYPE

SYNTAX AreaID

MAX-ACCESS read-only -- read-only since originally an
-- SMIv1 index

STATUS obsolete

DESCRIPTION

"The area that the address range is to be found
within."

REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"

::= { ospfAreaRangeEntry 1 }

ospfAreaRangeNet OBJECT-TYPE

SYNTAX IpAddress

MAX-ACCESS read-only -- read-only since originally an
-- SMIv1 index

STATUS obsolete

DESCRIPTION

"The IP address of the net or subnet indicated
by the range."

REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"

::= { ospfAreaRangeEntry 2 }

```

ospfAreaRangeMask OBJECT-TYPE
  SYNTAX      IpAddress
  MAX-ACCESS  read-create
  STATUS      obsolete
  DESCRIPTION
    "The subnet mask that pertains to the net or
     subnet."
  REFERENCE
    "OSPF Version 2, Appendix C.2 Area parameters"
 ::= { ospfAreaRangeEntry 3 }

ospfAreaRangeStatus OBJECT-TYPE
  SYNTAX      RowStatus
  MAX-ACCESS  read-create
  STATUS      obsolete
  DESCRIPTION
    "This object permits management of the table by
     facilitating actions such as row creation,
     construction, and destruction.

    The value of this object has no effect on
    whether other objects in this conceptual row can be
    modified."
 ::= { ospfAreaRangeEntry 4 }

ospfAreaRangeEffect OBJECT-TYPE
  SYNTAX      INTEGER {
    advertiseMatching (1),
    doNotAdvertiseMatching (2)
  }
  MAX-ACCESS  read-create
  STATUS      obsolete
  DESCRIPTION
    "Subnets subsumed by ranges either trigger the
     advertisement of the indicated summary
     (advertiseMatching) or result in the subnet's not
     being advertised at all outside the area."
  DEFVAL { advertiseMatching }
 ::= { ospfAreaRangeEntry 5 }

-- OSPF Host Table

ospfHostTable OBJECT-TYPE
  SYNTAX      SEQUENCE OF OspfHostEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The Host/Metric Table indicates what hosts are directly

```

attached to the router, what metrics and types of service should be advertised for them, and what areas they are found within."

REFERENCE

"OSPF Version 2, Appendix C.7 Host route parameters"
 $::= \{ \text{ospf} 6 \}$

ospfHostEntry OBJECT-TYPE

SYNTAX OspfHostEntry
 MAX-ACCESS not-accessible
 STATUS current
 DESCRIPTION

"A metric to be advertised, for a given type of service, when a given host is reachable.

Information in this table is persistent and when this object is written the entity SHOULD save the change to non-volatile storage."

INDEX { ospfHostIpAddress, ospfHostTOS }
 $::= \{ \text{ospfHostTable} 1 \}$

OspfHostEntry ::=

SEQUENCE {
 ospfHostIpAddress
 IpAddress,
 ospfHostTOS
 TOSType,
 ospfHostMetric
 Metric,
 ospfHostStatus
 RowStatus,
 ospfHostAreaID
 AreaID,
 ospfHostCfgAreaID
 AreaID
 }

ospfHostIpAddress OBJECT-TYPE

SYNTAX IpAddress
 MAX-ACCESS read-only -- read-only since originally an
 -- SMIV1 index
 STATUS current
 DESCRIPTION

"The IP address of the host."

REFERENCE

"OSPF Version 2, Appendix C.7 Host route parameters"
 $::= \{ \text{ospfHostEntry} 1 \}$

```

ospfHostTOS OBJECT-TYPE
  SYNTAX      TOSType
  MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
  STATUS      current
  DESCRIPTION
    "The Type of Service of the route being configured."
  REFERENCE
    "OSPF Version 2, Appendix C.7 Host route parameters"
 ::= { ospfHostEntry 2 }

ospfHostMetric OBJECT-TYPE
  SYNTAX      Metric
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The metric to be advertised."
  REFERENCE
    "OSPF Version 2, Appendix C.7 Host route parameters"
 ::= { ospfHostEntry 3 }

ospfHostStatus OBJECT-TYPE
  SYNTAX      RowStatus
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "This object permits management of the table by
     facilitating actions such as row creation,
     construction, and destruction.

    The value of this object has no effect on
    whether other objects in this conceptual row can be
    modified."
 ::= { ospfHostEntry 4 }

ospfHostAreaID OBJECT-TYPE
  SYNTAX      AreaID
  MAX-ACCESS  read-only
  STATUS      deprecated
  DESCRIPTION
    "The OSPF area to which the host belongs.
     Deprecated by ospfHostCfgAreaID."
  REFERENCE
    "OSPF Version 2, Appendix C.7 Host parameters"
 ::= { ospfHostEntry 5 }

ospfHostCfgAreaID OBJECT-TYPE
  SYNTAX      AreaID

```

```

MAX-ACCESS    read-create
STATUS        current
DESCRIPTION
  "To configure the OSPF area to which the host belongs."
REFERENCE
  "OSPF Version 2, Appendix C.7 Host parameters"
 ::= { ospfHostEntry 6 }

-- OSPF Interface Table

ospfIfTable OBJECT-TYPE
  SYNTAX      SEQUENCE OF OspfIfEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The OSPF Interface Table describes the interfaces
     from the viewpoint of OSPF.
    It augments the ipAddrTable with OSPF specific information."
REFERENCE
  "OSPF Version 2, Appendix C.3 Router interface
   parameters"
 ::= { ospf 7 }

ospfIfEntry OBJECT-TYPE
  SYNTAX      OspfIfEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The OSPF interface entry describes one interface
     from the viewpoint of OSPF.

Information in this table is persistent and when this object
is written the entity SHOULD save the change to non-volatile
storage."
INDEX { ospfIfIpAddress, ospfAddressLessIf }
 ::= { ospfIfTable 1 }

OspfIfEntry ::=
  SEQUENCE {
    ospfIfIpAddress
      IpAddress,
    ospfAddressLessIf
      InterfaceIndexOrZero,
    ospfIfAreaId
      AreaID,
    ospfIfType
      INTEGER,
    ospfIfAdminStat
  }

```

```

        Status,
ospfIfRtrPriority
    DesignatedRouterPriority,
ospfIfTransitDelay
    UpToMaxAge,
ospfIfRetransInterval
    UpToMaxAge,
ospfIfHelloInterval
    HelloRange,
ospfIfRtrDeadInterval
    PositiveInteger,
ospfIfPollInterval
    PositiveInteger,
ospfIfState
    INTEGER,
ospfIfDesignatedRouter
    IpAddress,
ospfIfBackupDesignatedRouter
    IpAddress,
ospfIfEvents
    Counter32,
ospfIfAuthKey
    OCTET STRING,
ospfIfStatus
    RowStatus,
ospfIfMulticastForwarding
    INTEGER,
ospfIfDemand
    TruthValue,
ospfIfAuthType
    OspfAuthenticationType,
ospfIfLsaCount
    Gauge32,
ospfIfLsaCksumSum
    Unsigned32,
ospfIfDesignatedRouterId
    RouterID,
ospfIfBackupDesignatedRouterId
    RouterID
}

ospfIfIpAddress OBJECT-TYPE
    SYNTAX      IpAddress
    MAX-ACCESS  read-only -- read-only since originally an
                      -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "The IP address of this OSPF interface."

```

```

 ::= { ospfIfEntry 1 }

ospfAddressLessIf OBJECT-TYPE
    SYNTAX      InterfaceIndexOrZero
    MAX-ACCESS  read-only -- read-only since originally an
                      -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "For the purpose of easing the instancing of
         addressed and addressless interfaces; this
         variable takes the value 0 on interfaces with
         IP addresses and the corresponding value of
         ifIndex for interfaces having no IP address."
 ::= { ospfIfEntry 2 }

ospfIfAreaId OBJECT-TYPE
    SYNTAX      AreaID
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "A 32-bit integer uniquely identifying the area
         to which the interface connects. Area ID
         0.0.0.0 is used for the OSPF backbone."
    DEFVAL { '00000000'H } -- 0.0.0.0
 ::= { ospfIfEntry 3 }

ospfIfType OBJECT-TYPE
    SYNTAX      INTEGER {
        broadcast (1),
        nbma (2),
        pointToPoint (3),
        pointToMultipoint (5)
    }
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "The OSPF interface type.
         By way of a default, this field may be intuited
         from the corresponding value of ifType.
         Broadcast LANs, such as Ethernet and IEEE 802.5,
         take the value 'broadcast', X.25 and similar
         technologies take the value 'nbma', and links
         that are definitively point to point take the
         value 'pointToPoint'."
 ::= { ospfIfEntry 4 }

ospfIfAdminStat OBJECT-TYPE
    SYNTAX      Status

```

```
MAX-ACCESS    read-create
STATUS        current
DESCRIPTION
  "The OSPF interface's administrative status.
  The value formed on the interface, and the interface
  will be advertised as an internal route to some area.
  The value 'disabled' denotes that the interface is
  external to OSPF."
DEFVAL { enabled }
 ::= { ospfIfEntry 5 }

ospfIfRtrPriority OBJECT-TYPE
 SYNTAX        DesignatedRouterPriority
 MAX-ACCESS    read-create
 STATUS        current
DESCRIPTION
  "The priority of this interface. Used in
  multi-access networks, this field is used in
  the designated router election algorithm. The
  value 0 signifies that the router is not eligible
  to become the designated router on this particular
  network. In the event of a tie in this value,
  routers will use their Router ID as a tie breaker."
DEFVAL { 1 }
 ::= { ospfIfEntry 6 }

ospfIfTransitDelay OBJECT-TYPE
 SYNTAX        UpToMaxAge
 UNITS         "seconds"
 MAX-ACCESS    read-create
 STATUS        current
DESCRIPTION
  "The estimated number of seconds it takes to
  transmit a link state update packet over this
  interface. Note that the minimal value SHOULD be
  1 second."
DEFVAL { 1 }
 ::= { ospfIfEntry 7 }

ospfIfRetransInterval OBJECT-TYPE
 SYNTAX        UpToMaxAge
 UNITS         "seconds"
 MAX-ACCESS    read-create
 STATUS        current
DESCRIPTION
  "The number of seconds between link state advertisement
  retransmissions, for adjacencies belonging to this
  interface. This value is also used when retransmitting
```

```

database description and Link State request packets.
Note that minimal value SHOULD be 1 second."
DEFVAL { 5 }
 ::= { ospfIfEntry 8 }

ospfIfHelloInterval OBJECT-TYPE
    SYNTAX      HelloRange
    UNITS       "seconds"
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "The length of time, in seconds, between the Hello packets
         that the router sends on the interface. This value must be
         the same for all routers attached to a common network."
DEFVAL { 10 }
 ::= { ospfIfEntry 9 }

ospfIfRtrDeadInterval OBJECT-TYPE
    SYNTAX      PositiveInteger
    UNITS       "seconds"
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "The number of seconds that a router's Hello packets have
         not been seen before its neighbors declare the router down.
         This should be some multiple of the Hello interval. This
         value must be the same for all routers attached to a common
         network."
DEFVAL { 40 }
 ::= { ospfIfEntry 10 }

ospfIfPollInterval OBJECT-TYPE
    SYNTAX      PositiveInteger
    UNITS       "seconds"
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION
        "The larger time interval, in seconds, between the Hello
         packets sent to an inactive non-broadcast multi-access
         neighbor."
DEFVAL { 120 }
 ::= { ospfIfEntry 11 }

ospfIfState OBJECT-TYPE
    SYNTAX      INTEGER {
                  down (1),
                  loopback (2),
                  waiting (3),

```

```
        pointToPoint (4),
        designatedRouter (5),
        backupDesignatedRouter (6),
        otherDesignatedRouter (7)
    }
MAX-ACCESS    read-only
STATUS        current
DESCRIPTION   "The OSPF Interface State."
DEFVAL { down }
 ::= { ospfIfEntry 12 }

ospfIfDesignatedRouter OBJECT-TYPE
    SYNTAX      IpAddress
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The IP address of the designated router."
DEFVAL { '00000000'H } -- 0.0.0.0
 ::= { ospfIfEntry 13 }

ospfIfBackupDesignatedRouter OBJECT-TYPE
    SYNTAX      IpAddress
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The IP address of the backup designated
                 router."
DEFVAL { '00000000'H } -- 0.0.0.0
 ::= { ospfIfEntry 14 }

ospfIfEvents OBJECT-TYPE
    SYNTAX      Counter32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The number of times this OSPF interface has
                 changed its state or an error has occurred.

                 Discontinuities in the value of this counter can occur
                 at re-initialization of the management system, and at other
                 times as indicated by the value of ospfDiscontinuityTime."
 ::= { ospfIfEntry 15 }

ospfIfAuthKey OBJECT-TYPE
    SYNTAX      OCTET STRING (SIZE (0..256))
    MAX-ACCESS  read-create
    STATUS      current
```

DESCRIPTION

"The cleartext password used as an OSPF authentication key when simplePassword security is enabled. This object does not access any OSPF cryptographic (e.g., MD5) authentication key under any circumstance.

If the key length is shorter than 8 octets, the agent will left adjust and zero fill to 8 octets.

Unauthenticated interfaces need no authentication key, and simple password authentication cannot use a key of more than 8 octets.

Note that the use of simplePassword authentication is NOT recommended when there is concern regarding attack upon the OSPF system. SimplePassword authentication is only sufficient to protect against accidental misconfigurations because it re-uses cleartext passwords [RFC1704].

When read, ospfIfAuthKey always returns an octet string of length zero."

REFERENCE

"OSPF Version 2, Section 9 The Interface Data Structure"

```
DEFVAL { '0000000000000000'H } -- 0.0.0.0.0.0.0
 ::= { ospfIfEntry 16 }
```

ospfIfStatus OBJECT-TYPE

SYNTAX	RowStatus
MAX-ACCESS	read-create
STATUS	current

DESCRIPTION

"This object permits management of the table by facilitating actions such as row creation, construction, and destruction.

The value of this object has no effect on whether other objects in this conceptual row can be modified."

```
 ::= { ospfIfEntry 17 }
```

ospfIfMulticastForwarding OBJECT-TYPE

SYNTAX	INTEGER {
	blocked (1), -- no multicast forwarding
	multicast (2), -- using multicast address
	unicast (3) -- to each OSPF neighbor

```

        }
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
  "The way multicasts should be forwarded on this
  interface: not forwarded, forwarded as data
  link multicasts, or forwarded as data link
  unicasts. Data link multicasting is not
  meaningful on point-to-point and NBMA interfaces,
  and setting ospfMulticastForwarding to 0 effectively
  disables all multicast forwarding."
DEFVAL { blocked }
 ::= { ospfIfEntry 18 }

ospfIfDemand OBJECT-TYPE
  SYNTAX      TruthValue
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "Indicates whether Demand OSPF procedures (hello
     suppression to FULL neighbors and setting the
     DoNotAge flag on propagated LSAs) should be
     performed on this interface."
DEFVAL { false }
 ::= { ospfIfEntry 19 }

ospfIfAuthType OBJECT-TYPE
  SYNTAX      OspfAuthenticationType
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The authentication type specified for an interface.

    Note that this object can be used to engage
    in significant attacks against an OSPF router."
REFERENCE
  "OSPF Version 2, Appendix D Authentication"
DEFVAL { none } -- no authentication, by default
 ::= { ospfIfEntry 20 }

ospfIfLsaCount OBJECT-TYPE
  SYNTAX      Gauge32
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "The total number of link-local link state advertisements
     in this interface's link-local link state database."
 ::= { ospfIfEntry 21 }

```

```

ospfIfLsaCksumSum OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The 32-bit unsigned sum of the Link State
         Advertisements' LS checksums contained in this
         interface's link-local link state database.
         The sum can be used to determine if there has
         been a change in the interface's link state
         database and to compare the interface link state
         database of routers attached to the same subnet."
 ::= { ospfIfEntry 22 }

```

```

ospfIfDesignatedRouterId OBJECT-TYPE
    SYNTAX      RouterID
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The Router ID of the designated router."
 ::= { ospfIfEntry 23 }

```

```

ospfIfBackupDesignatedRouterId OBJECT-TYPE
    SYNTAX      RouterID
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The Router ID of the backup designated router."
 ::= { ospfIfEntry 24 }

```

-- OSPF Interface Metric Table

```

ospfIfMetricTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfIfMetricEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The Metric Table describes the metrics to be advertised
         for a specified interface at the various types of service.
         As such, this table is an adjunct of the OSPF Interface
         Table."

```

Types of service, as defined by RFC 791, have the ability
to request low delay, high bandwidth, or reliable linkage.

For the purposes of this specification, the measure of
bandwidth:

Metric = referenceBandwidth / ifSpeed
 is the default value.
 The default reference bandwidth is 10^8 .
 For multiple link interfaces, note that ifSpeed is the sum
 of the individual link speeds. This yields a number having
 the following typical values:

Network Type/bit rate Metric

>= 100 MBPS	1
Ethernet/802.3	10
E1	48
T1 (ESF)	65
64 KBPS	1562
56 KBPS	1785
19.2 KBPS	5208
9.6 KBPS	10416

Routes that are not specified use the default
 (TOS 0) metric.

Note that the default reference bandwidth can be configured
 using the general group object ospfReferenceBandwidth."

REFERENCE

"OSPF Version 2, Appendix C.3 Router interface
 parameters"
 $::= \{ \text{ospf } 8 \}$

ospfIfMetricEntry OBJECT-TYPE
 SYNTAX OspfIfMetricEntry
 MAX-ACCESS not-accessible
 STATUS current
 DESCRIPTION
 "A particular TOS metric for a non-virtual interface
 identified by the interface index.

Information in this table is persistent and when this object
 is written the entity SHOULD save the change to non-volatile
 storage."

REFERENCE

"OSPF Version 2, Appendix C.3 Router interface
 parameters"
 INDEX { ospfIfMetricIpAddress,
 ospfIfMetricAddressLessIf,
 ospfIfMetricTOS }
 $::= \{ \text{ospfIfMetricTable } 1 \}$

```

OspfIfMetricEntry ::= 
SEQUENCE {
    ospfIfMetricIpAddress
        IpAddress,
    ospfIfMetricAddressLessIf
        InterfaceIndexOrZero,
    ospfIfMetricTOS
        TOSType,
    ospfIfMetricValue
        Metric,
    ospfIfMetricStatus
        RowStatus
}
}

ospfIfMetricIpAddress OBJECT-TYPE
SYNTAX      IpAddress
MAX-ACCESS  read-only -- read-only since originally an
           -- SMIv1 index
STATUS      current
DESCRIPTION
"The IP address of this OSPF interface. On row
creation, this can be derived from the instance."
::= { ospfIfMetricEntry 1 }

ospfIfMetricAddressLessIf OBJECT-TYPE
SYNTAX      InterfaceIndexOrZero
MAX-ACCESS  read-only -- read-only since originally an
           -- SMIv1 index
STATUS      current
DESCRIPTION
"For the purpose of easing the instancing of
addressed and addressless interfaces; this
variable takes the value 0 on interfaces with
IP addresses and the value of ifIndex for
interfaces having no IP address. On row
creation, this can be derived from the instance."
::= { ospfIfMetricEntry 2 }

ospfIfMetricTOS OBJECT-TYPE
SYNTAX      TOSType
MAX-ACCESS  read-only -- read-only since originally an
           -- SMIv1 index
STATUS      current
DESCRIPTION
"The Type of Service metric being referenced.
On row creation, this can be derived from the
instance."
::= { ospfIfMetricEntry 3 }

```

```
ospfIfMetricValue OBJECT-TYPE
  SYNTAX      Metric
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The metric of using this Type of Service on
     this interface. The default value of the TOS 0
     metric is 10^8 / ifSpeed."
 ::= { ospfIfMetricEntry 4 }

ospfIfMetricStatus OBJECT-TYPE
  SYNTAX      RowStatus
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "This object permits management of the table by
     facilitating actions such as row creation,
     construction, and destruction.

    The value of this object has no effect on
    whether other objects in this conceptual row can be
    modified."
 ::= { ospfIfMetricEntry 5 }

-- OSPF Virtual Interface Table

ospfVirtIfTable OBJECT-TYPE
  SYNTAX      SEQUENCE OF OspfVirtIfEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "Information about this router's virtual interfaces
     that the OSPF Process is configured to carry on."
  REFERENCE
    "OSPF Version 2, Appendix C.4  Virtual link
     parameters"
 ::= { ospf 9 }

ospfVirtIfEntry OBJECT-TYPE
  SYNTAX      OspfVirtIfEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "Information about a single virtual interface.

    Information in this table is persistent and when this object
    is written the entity SHOULD save the change to non-volatile
    storage."

```

```

INDEX { ospfvirtifareaid, ospfvirtifneighbor }
::= { ospfvirtiftable 1 }

Ospfvirtifentry ::= 
SEQUENCE {
    ospfvirtifareaid
        AreaID,
    ospfvirtifneighbor
        RouterID,
    ospfvirtiftransitdelay
        UpToMaxAge,
    ospfvirtifretransinterval
        UpToMaxAge,
    ospfvirtifhellointerval
        HelloRange,
    ospfvirtifrtrdeadinterval
        PositiveInteger,
    ospfvirtifstate
        INTEGER,
    ospfvirtifevents
        Counter32,
    ospfvirtifauthkey
        OCTET STRING,
    ospfvirtifstatus
        RowStatus,
    ospfvirtifauthtype
        OspfAuthenticationType,
    ospfvirtiflsacount
        Gauge32,
    ospfvirtiflsacksumsum
        Unsigned32
}

ospfvirtifareaid OBJECT-TYPE
    SYNTAX      AreaID
    MAX-ACCESS  read-only -- read-only since originally an
                    -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "The transit area that the virtual link
         traverses. By definition, this is not 0.0.0.0."
    ::= { ospfvirtifentry 1 }

ospfvirtifneighbor OBJECT-TYPE
    SYNTAX      RouterID
    MAX-ACCESS  read-only -- read-only since originally an
                    -- SMIv1 index
    STATUS      current

```

```
DESCRIPTION
  "The Router ID of the virtual neighbor."
 ::= { ospfVirtIfEntry 2 }

ospfVirtIfTransitDelay OBJECT-TYPE
  SYNTAX      UpToMaxAge
  UNITS       "seconds"
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The estimated number of seconds it takes to
     transmit a Link State update packet over this
     interface. Note that the minimal value SHOULD be
     1 second."
  DEFVAL { 1 }
 ::= { ospfVirtIfEntry 3 }

ospfVirtIfRetransInterval OBJECT-TYPE
  SYNTAX      UpToMaxAge
  UNITS       "seconds"
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The number of seconds between link state
     advertisement retransmissions, for adjacencies
     belonging to this interface. This value is
     also used when retransmitting database
     description and Link State request packets. This
     value should be well over the expected
     round-trip time. Note that the minimal value SHOULD be
     1 second."
  DEFVAL { 5 }
 ::= { ospfVirtIfEntry 4 }

ospfVirtIfHelloInterval OBJECT-TYPE
  SYNTAX      HelloRange
  UNITS       "seconds"
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The length of time, in seconds, between the
     Hello packets that the router sends on the
     interface. This value must be the same for the
     virtual neighbor."
  DEFVAL { 10 }
 ::= { ospfVirtIfEntry 5 }

ospfVirtIfRtrDeadInterval OBJECT-TYPE
```

```

SYNTAX      PositiveInteger
UNITS      "seconds"
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
  "The number of seconds that a router's Hello
  packets have not been seen before its
  neighbors declare the router down. This should be
  some multiple of the Hello interval. This
  value must be the same for the virtual neighbor."
DEFVAL { 60 }
 ::= { ospfVirtIfEntry 6 }

ospfVirtIfState OBJECT-TYPE
  SYNTAX      INTEGER {
    down (1), -- these use the same encoding
    pointToPoint (4) -- as the ospfIfTable
  }
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "OSPF virtual interface states."
  DEFVAL { down }
  ::= { ospfVirtIfEntry 7 }

ospfVirtIfEvents OBJECT-TYPE
  SYNTAX      Counter32
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "The number of state changes or error events on
    this virtual link.

    Discontinuities in the value of this counter can occur
    at re-initialization of the management system, and at other
    times as indicated by the value of ospfDiscontinuityTime."
  ::= { ospfVirtIfEntry 8 }

ospfVirtIfAuthKey OBJECT-TYPE
  SYNTAX      OCTET STRING (SIZE(0..256))
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "The cleartext password used as an OSPF
    authentication key when simplePassword security
    is enabled. This object does not access any OSPF
    cryptographic (e.g., MD5) authentication key under
    any circumstance.

```

If the key length is shorter than 8 octets, the agent will left adjust and zero fill to 8 octets.

Unauthenticated interfaces need no authentication key, and simple password authentication cannot use a key of more than 8 octets.

Note that the use of simplePassword authentication is NOT recommended when there is concern regarding attack upon the OSPF system. SimplePassword authentication is only sufficient to protect against accidental misconfigurations because it re-uses cleartext passwords. [RFC1704]

When read, ospfIfAuthKey always returns an octet string of length zero."

REFERENCE

"OSPF Version 2, Section 9 The Interface Data Structure"

```
DEFVAL { '0000000000000000'H } -- 0.0.0.0.0.0.0
 ::= { ospfVirtIfEntry 9 }
```

ospfVirtIfStatus OBJECT-TYPE

SYNTAX	RowStatus
MAX-ACCESS	read-create
STATUS	current

DESCRIPTION

"This object permits management of the table by facilitating actions such as row creation, construction, and destruction.

The value of this object has no effect on whether other objects in this conceptual row can be modified."

```
::= { ospfVirtIfEntry 10 }
```

ospfVirtIfAuthType OBJECT-TYPE

SYNTAX	OspfAuthenticationType
MAX-ACCESS	read-create
STATUS	current

DESCRIPTION

"The authentication type specified for a virtual interface.

Note that this object can be used to engage in significant attacks against an OSPF router."

REFERENCE

"OSPF Version 2, Appendix E Authentication"

```
DEFVAL { none } -- no authentication, by default
```

```

 ::= { ospfVirtIfEntry 11 }

ospfVirtIfLsaCount OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The total number of link-local link state advertisements
         in this virtual interface's link-local link state database."
 ::= { ospfVirtIfEntry 12 }

ospfVirtIfLsaCksumSum OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The 32-bit unsigned sum of the link state
         advertisements' LS checksums contained in this
         virtual interface's link-local link state database.
         The sum can be used to determine if there has
         been a change in the virtual interface's link state
         database, and to compare the virtual interface
         link state database of the virtual neighbors."
 ::= { ospfVirtIfEntry 13 }

-- OSPF Neighbor Table

ospfNbrTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfNbrEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "A table describing all non-virtual neighbors
         in the locality of the OSPF router."
    REFERENCE
        "OSPF Version 2, Section 10 The Neighbor Data
         Structure"
 ::= { ospf 10 }

ospfNbrEntry OBJECT-TYPE
    SYNTAX      OspfNbrEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The information regarding a single neighbor.

        Information in this table is persistent and when this object
        is written the entity SHOULD save the change to non-volatile

```

```

storage."
REFERENCE
  "OSPF Version 2, Section 10 The Neighbor Data
  Structure"
INDEX { ospfNbrIpAddr, ospfNbrAddressLessIndex }
 ::= { ospfNbrTable 1 }

OspfNbrEntry ::= 
SEQUENCE {
  ospfNbrIpAddr
    IpAddress,
  ospfNbrAddressLessIndex
    InterfaceIndexOrZero,
  ospfNbrRtrId
    RouterID,
  ospfNbrOptions
    Integer32,
  ospfNbrPriority
    DesignatedRouterPriority,
  ospfNbrState
    INTEGER,
  ospfNbrEvents
    Counter32,
  ospfNbrLsRetransQLen
    Gauge32,
  ospfNbmaNbrStatus
    RowStatus,
  ospfNbmaNbrPermanence
    INTEGER,
  ospfNbrHelloSuppressed
    TruthValue,
  ospfNbrRestartHelperStatus
    INTEGER,
  ospfNbrRestartHelperAge
    Unsigned32,
  ospfNbrRestartHelperExitReason
    INTEGER
}

ospfNbrIpAddr OBJECT-TYPE
  SYNTAX      IpAddress
  MAX-ACCESS  read-only -- read-only since originally an
                      -- SMIv1 index
  STATUS      current
  DESCRIPTION
    "The IP address this neighbor is using in its
     IP source address. Note that, on addressless
     links, this will not be 0.0.0.0 but the

```

```

address of another of the neighbor's interfaces."
 ::= { ospfNbrEntry 1 }

ospfNbrAddressLessIndex OBJECT-TYPE
    SYNTAX      InterfaceIndexOrZero
    MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "On an interface having an IP address, zero.
         On addressless interfaces, the corresponding
         value of ifIndex in the Internet Standard MIB.
         On row creation, this can be derived from the
         instance."
 ::= { ospfNbrEntry 2 }

ospfNbrRtrId OBJECT-TYPE
    SYNTAX      RouterID
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "A 32-bit integer (represented as a type
         InetAddress) uniquely identifying the neighboring
         router in the Autonomous System."
    DEFVAL { '00000000'H } -- 0.0.0.0
 ::= { ospfNbrEntry 3 }

ospfNbrOptions OBJECT-TYPE
    SYNTAX      Integer32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "A bit mask corresponding to the neighbor's
         options field.

         Bit 0, if set, indicates that the system will
         operate on Type of Service metrics other than
         TOS 0. If zero, the neighbor will ignore all
         metrics except the TOS 0 metric.

         Bit 1, if set, indicates that the associated
         area accepts and operates on external
         information; if zero, it is a stub area.

         Bit 2, if set, indicates that the system is
         capable of routing IP multicast datagrams, that is
         that it implements the multicast extensions to
         OSPF.

         "

```

Bit 3, if set, indicates that the associated area is an NSSA. These areas are capable of carrying type-7 external advertisements, which are translated into type-5 external advertisements at NSSA borders."

REFERENCE

"OSPF Version 2, Section 12.1.2 Options"

DEFVAL { 0 }

::= { ospfNbrEntry 4 }

ospfNbrPriority OBJECT-TYPE

SYNTAX DesignatedRouterPriority

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"The priority of this neighbor in the designated router election algorithm. The value 0 signifies that the neighbor is not eligible to become the designated router on this particular network."

DEFVAL { 1 }

::= { ospfNbrEntry 5 }

ospfNbrState OBJECT-TYPE

SYNTAX INTEGER {

down (1),
attempt (2),
init (3),
twoWay (4),
exchangeStart (5),
exchange (6),
loading (7),
full (8)
}

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"The state of the relationship with this neighbor."

REFERENCE

"OSPF Version 2, Section 10.1 Neighbor States"

DEFVAL { down }

::= { ospfNbrEntry 6 }

ospfNbrEvents OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"The number of times this neighbor relationship has changed state or an error has occurred.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of ospfDiscontinuityTime."

```
::= { ospfNbrEntry 7 }
```

ospfNbrLsRetransQLen OBJECT-TYPE

SYNTAX	Gauge32
MAX-ACCESS	read-only
STATUS	current
DESCRIPTION	"The current length of the retransmission queue."

```
::= { ospfNbrEntry 8 }
```

ospfNbmaNbrStatus OBJECT-TYPE

SYNTAX	RowStatus
MAX-ACCESS	read-create
STATUS	current
DESCRIPTION	"This object permits management of the table by facilitating actions such as row creation, construction, and destruction.

The value of this object has no effect on whether other objects in this conceptual row can be modified."

```
::= { ospfNbrEntry 9 }
```

ospfNbmaNbrPermanence OBJECT-TYPE

SYNTAX	INTEGER { dynamic (1), -- learned through protocol permanent (2) -- configured address }
MAX-ACCESS	read-only
STATUS	current
DESCRIPTION	"This variable displays the status of the entry; 'dynamic' and 'permanent' refer to how the neighbor became known."
DEFVAL	{ permanent }

```
::= { ospfNbrEntry 10 }
```

ospfNbrHelloSuppressed OBJECT-TYPE

SYNTAX	TruthValue
MAX-ACCESS	read-only

```

STATUS      current
DESCRIPTION
  "Indicates whether Hellos are being suppressed
  to the neighbor."
 ::= { ospfNbrEntry 11 }

ospfNbrRestartHelperStatus OBJECT-TYPE
  SYNTAX      INTEGER { notHelping (1),
                      helping (2)
                      }
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
  "Indicates whether the router is acting
  as a graceful restart helper for the neighbor."
 ::= { ospfNbrEntry 12 }

ospfNbrRestartHelperAge OBJECT-TYPE
  SYNTAX      Unsigned32
  UNITS       "seconds"
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
  "Remaining time in current OSPF graceful restart
  interval, if the router is acting as a restart
  helper for the neighbor."
 ::= { ospfNbrEntry 13 }

ospfNbrRestartHelperExitReason OBJECT-TYPE
  SYNTAX      INTEGER { none (1),          -- not attempted
                      inProgress (2),    -- restart in
                      completed (3),     -- progress
                      successfully (4),  -- completed
                      timedOut (5)       -- successfully
                      topologyChanged (5) -- timed out
                      topologyChanged (5) -- aborted due to
                      topology           -- change.
                      }
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
  "Describes the outcome of the last attempt at acting
  as a graceful restart helper for the neighbor."
 ::= { ospfNbrEntry 14 }

-- OSPF Virtual Neighbor Table

```

```

ospfVirtNbrTable OBJECT-TYPE
  SYNTAX      SEQUENCE OF OspfVirtNbrEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "This table describes all virtual neighbors.
     Since virtual links are configured
     in the Virtual Interface Table, this table is read-only."
  REFERENCE
    "OSPF Version 2, Section 15 Virtual Links"
 ::= { ospf 11 }

ospfVirtNbrEntry OBJECT-TYPE
  SYNTAX      OspfVirtNbrEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "Virtual neighbor information."
  INDEX { ospfVirtNbrArea, ospfVirtNbrRtrId }
 ::= { ospfVirtNbrTable 1 }

OspfVirtNbrEntry ::=
  SEQUENCE {
    ospfVirtNbrArea
      AreaID,
    ospfVirtNbrRtrId
      RouterID,
    ospfVirtNbrIpAddr
     IpAddress,
    ospfVirtNbrOptions
      Integer32,
    ospfVirtNbrState
      INTEGER,
    ospfVirtNbrEvents
      Counter32,
    ospfVirtNbrLsRetransQLen
      Gauge32,
    ospfVirtNbrHelloSuppressed
      TruthValue,
    ospfVirtNbrRestartHelperStatus
      INTEGER,
    ospfVirtNbrRestartHelperAge
      Unsigned32,
    ospfVirtNbrRestartHelperExitReason
      INTEGER
  }

ospfVirtNbrArea OBJECT-TYPE

```

```

SYNTAX      AreaID
MAX-ACCESS  read-only -- read-only since originally an
             -- SMIv1 index
STATUS      current
DESCRIPTION
    "The Transit Area Identifier."
 ::= { ospfVirtNbrEntry 1 }

ospfVirtNbrRtrId OBJECT-TYPE
    SYNTAX      RouterID
    MAX-ACCESS  read-only -- read-only since originally an
                     -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "A 32-bit integer uniquely identifying the
         neighboring router in the Autonomous System."
 ::= { ospfVirtNbrEntry 2 }

ospfVirtNbrIpAddr OBJECT-TYPE
    SYNTAX      IpAddress
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The IP address this virtual neighbor is using."
 ::= { ospfVirtNbrEntry 3 }

ospfVirtNbrOptions OBJECT-TYPE
    SYNTAX      Integer32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "A bit mask corresponding to the neighbor's
         options field.

        Bit 1, if set, indicates that the system will
        operate on Type of Service metrics other than
        TOS 0.  If zero, the neighbor will ignore all
        metrics except the TOS 0 metric.

        Bit 2, if set, indicates that the system is
        network multicast capable, i.e., that it
        implements OSPF multicast routing."
 ::= { ospfVirtNbrEntry 4 }

ospfVirtNbrState OBJECT-TYPE
    SYNTAX      INTEGER {
                  down (1),
                  attempt (2),

```

```

        init (3),
        twoWay (4),
        exchangeStart (5),
        exchange (6),
        loading (7),
        full (8)
    }
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The state of the virtual neighbor relationship."
::= { ospfVirtNbrEntry 5 }

ospfVirtNbrEvents OBJECT-TYPE
    SYNTAX      Counter32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The number of times this virtual link has
         changed its state or an error has occurred.

         Discontinuities in the value of this counter can occur
         at re-initialization of the management system, and at other
         times as indicated by the value of ospfDiscontinuityTime."
::= { ospfVirtNbrEntry 6 }

ospfVirtNbrLsRetransQLen OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The current length of the retransmission
         queue."
::= { ospfVirtNbrEntry 7 }

ospfVirtNbrHelloSuppressed OBJECT-TYPE
    SYNTAX      TruthValue
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "Indicates whether Hellos are being suppressed
         to the neighbor."
::= { ospfVirtNbrEntry 8 }

ospfVirtNbrRestartHelperStatus OBJECT-TYPE
    SYNTAX      INTEGER { notHelping (1),
                           helping (2)
                         }

```

```

MAX-ACCESS    read-only
STATUS        current
DESCRIPTION
  "Indicates whether the router is acting
  as a graceful restart helper for the neighbor."
 ::= { ospfVirtNbrEntry 9 }

ospfVirtNbrRestartHelperAge OBJECT-TYPE
  SYNTAX      Unsigned32
  UNITS       "seconds"
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "Remaining time in current OSPF graceful restart
     interval, if the router is acting as a restart
     helper for the neighbor."
 ::= { ospfVirtNbrEntry 10 }

ospfVirtNbrRestartHelperExitReason OBJECT-TYPE
  SYNTAX      INTEGER { none(1),          -- not attempted
                      inProgress(2),      -- restart in
                      completed(3),       -- successfully
                      timedOut(4),        -- completed
                      topologyChanged(5) -- timed out
                                         -- aborted due to
                                         -- topology
                                         -- change.
}
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "Describes the outcome of the last attempt at acting
     as a graceful restart helper for the neighbor."
 ::= { ospfVirtNbrEntry 11 }

-- OSPF Link State Database, External

ospfExtLsdbTable OBJECT-TYPE
  SYNTAX      SEQUENCE OF OspfExtLsdbEntry
  MAX-ACCESS  not-accessible
  STATUS      deprecated
  DESCRIPTION
    "The OSPF Process's external LSA link state database.

    This table is identical to the OSPF LSDB Table
    in format, but contains only external link state
    advertisements. The purpose is to allow external

```

LSAs to be displayed once for the router rather than once in each non-stub area.

Note that external LSAs are also in the AS-scope link state database."

REFERENCE

"OSPF Version 2, Section 12 Link State Advertisements"
 $::= \{ \text{ospf} 12 \}$

```
ospfExtLsdbEntry OBJECT-TYPE
    SYNTAX      OspfExtLsdbEntry
    MAX-ACCESS  not-accessible
    STATUS      deprecated
    DESCRIPTION
        "A single link state advertisement."
    INDEX { ospfExtLsdbType, ospfExtLsdbLsid, ospfExtLsdbRouterId }
    ::= { ospfExtLsdbTable 1 }
```

```
OspfExtLsdbEntry ::=
    SEQUENCE {
        ospfExtLsdbType
            INTEGER,
        ospfExtLsdbLsid
           IpAddress,
        ospfExtLsdbRouterId
            RouterID,
        ospfExtLsdbSequence
            Integer32,
        ospfExtLsdbAge
            Integer32,
        ospfExtLsdbChecksum
            Integer32,
        ospfExtLsdbAdvertisement
            OCTET STRING
    }
```

```
ospfExtLsdbType OBJECT-TYPE
    SYNTAX      INTEGER {
        asExternalLink (5)
    }
    MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
    STATUS      deprecated
    DESCRIPTION
        "The type of the link state advertisement.
         Each link state type has a separate advertisement
         format."
    REFERENCE
```

```

"OSPF Version 2, Appendix A.4.1 The Link State
Advertisement header"

 ::= { ospfExtLsdbEntry 1 }

ospfExtLsdbLsid OBJECT-TYPE
    SYNTAX      IpAddress
    MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
    STATUS      deprecated
    DESCRIPTION
        "The Link State ID is an LS Type Specific field
         containing either a Router ID or an IP address;
         it identifies the piece of the routing domain
         that is being described by the advertisement."
    REFERENCE
        "OSPF Version 2, Section 12.1.4 Link State ID"
    ::= { ospfExtLsdbEntry 2 }

ospfExtLsdbRouterId OBJECT-TYPE
    SYNTAX      RouterID
    MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
    STATUS      deprecated
    DESCRIPTION
        "The 32-bit number that uniquely identifies the
         originating router in the Autonomous System."
    REFERENCE
        "OSPF Version 2, Appendix C.1 Global parameters"
    ::= { ospfExtLsdbEntry 3 }

ospfExtLsdbSequence OBJECT-TYPE
    SYNTAX      Integer32
    MAX-ACCESS  read-only
    STATUS      deprecated
    DESCRIPTION
        "The sequence number field is a signed 32-bit
         integer. It starts with the value '80000001'h,
         or '-7FFFFFFF'h, and increments until '7FFFFFFF'h.
         Thus, a typical sequence number will be very negative.
         It is used to detect old and duplicate link state
         advertisements. The space of sequence numbers is linearly
         ordered. The larger the sequence number, the more recent
         the advertisement."
    REFERENCE
        "OSPF Version 2, Section 12.1.6 LS sequence
         number"
    ::= { ospfExtLsdbEntry 4 }

```

```

ospfExtLsdbAge OBJECT-TYPE
  SYNTAX      Integer32 -- Should be 0..MaxAge, except when
                  -- doNotAge bit is set
  UNITS       "seconds"
  MAX-ACCESS  read-only
  STATUS      deprecated
  DESCRIPTION
    "This field is the age of the link state
     advertisement in seconds."
  REFERENCE
    "OSPF Version 2, Section 12.1.1 LS age"
    ::= { ospfExtLsdbEntry 5 }

ospfExtLsdbChecksum OBJECT-TYPE
  SYNTAX      Integer32
  MAX-ACCESS  read-only
  STATUS      deprecated
  DESCRIPTION
    "This field is the checksum of the complete
     contents of the advertisement, excepting the
     age field. The age field is excepted so that
     an advertisement's age can be incremented
     without updating the checksum. The checksum
     used is the same that is used for ISO
     connectionless datagrams; it is commonly referred
     to as the Fletcher checksum."
  REFERENCE
    "OSPF Version 2, Section 12.1.7 LS checksum"
    ::= { ospfExtLsdbEntry 6 }

ospfExtLsdbAdvertisement OBJECT-TYPE
  SYNTAX      OCTET STRING (SIZE(36))
  MAX-ACCESS  read-only
  STATUS      deprecated
  DESCRIPTION
    "The entire link state advertisement, including
     its header."
  REFERENCE
    "OSPF Version 2, Section 12 Link State
     Advertisements"
    ::= { ospfExtLsdbEntry 7 }

-- OSPF Use of the CIDR Route Table

  ospfRouteGroup   OBJECT IDENTIFIER ::= { ospf 13 }

-- The IP Forwarding Table defines a number of objects for use by
-- the routing protocol to externalize its information. Most of

```

```

--      the variables (ipForwardDest, ipForwardMask, ipForwardPolicy,
--      ipForwardNextHop, ipForwardIfIndex, ipForwardType,
--      ipForwardProto, ipForwardAge, and ipForwardNextHopAS) are
--      defined there.

--      Those that leave some discretion are defined here.

--      ipCidrRouteProto is, of course, ospf (13).

--      ipCidrRouteAge is the time since the route was first
--      calculated, as opposed to the time since the last SPF run.
--      ipCidrRouteInfo is an OBJECT IDENTIFIER for use by the routing
--      protocol. The following values shall be found there depending
--      on the way the route was calculated.

ospfIntraArea      OBJECT IDENTIFIER ::= { ospfRouteGroup 1 }
ospfInterArea      OBJECT IDENTIFIER ::= { ospfRouteGroup 2 }
ospfExternalType1  OBJECT IDENTIFIER ::= { ospfRouteGroup 3 }
ospfExternalType2  OBJECT IDENTIFIER ::= { ospfRouteGroup 4 }

--      ipCidrRouteMetric1 is, by definition, the primary routing
--      metric. Therefore, it should be the metric that route
--      selection is based on. For intra-area and inter-area routes,
--      it is an OSPF metric. For External Type 1 (comparable value)
--      routes, it is an OSPF metric plus the External Metric. For
--      external Type 2 (non-comparable value) routes, it is the
--      external metric.

--      ipCidrRouteMetric2 is, by definition, a secondary routing
--      metric. Therefore, it should be the metric that breaks a tie
--      among routes having equal metric1 values and the same
--      calculation rule. For intra-area, inter-area routes, and
--      External Type 1 (comparable value) routes, it is unused. For
--      External Type 2 (non-comparable value) routes, it is the metric
--      to the AS border router.

--      ipCidrRouteMetric3, ipCidrRouteMetric4, and ipCidrRouteMetric5
--      are unused.

--      The OSPF Area Aggregate Table

--      This table replaces the OSPF Area Summary Table, being an
--      extension of that for CIDR routers.

ospfAreaAggregateTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfAreaAggregateEntry
    MAX-ACCESS  not-accessible
    STATUS      current

```

DESCRIPTION

"The Area Aggregate Table acts as an adjunct to the Area Table. It describes those address aggregates that are configured to be propagated from an area. Its purpose is to reduce the amount of information that is known beyond an Area's borders.

It contains a set of IP address ranges specified by an IP address/IP network mask pair. For example, a class B address range of X.X.X.X with a network mask of 255.255.0.0 includes all IP addresses from X.X.0.0 to X.X.255.255.

Note that if ranges are configured such that one range subsumes another range (e.g., 10.0.0.0 mask 255.0.0.0 and 10.1.0.0 mask 255.255.0.0), the most specific match is the preferred one."

REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"
`::= { ospf 14 }`

ospfAreaAggregateEntry OBJECT-TYPE

SYNTAX OspfAreaAggregateEntry
 MAX-ACCESS not-accessible
 STATUS current
 DESCRIPTION

"A single area aggregate entry.

Information in this table is persistent and when this object is written the entity SHOULD save the change to non-volatile storage."

REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"
 INDEX { ospfAreaAggregateAreaID, ospfAreaAggregateLsdbType,
 ospfAreaAggregateNet, ospfAreaAggregateMask }
`::= { ospfAreaAggregateTable 1 }`

OspfAreaAggregateEntry ::=

```
SEQUENCE {
  ospfAreaAggregateAreaID
    AreaID,
  ospfAreaAggregateLsdbType
    INTEGER,
  ospfAreaAggregateNet
   IpAddress,
  ospfAreaAggregateMask
    IpAddress,
  ospfAreaAggregateStatus}
```

```

    RowStatus,
    ospfAreaAggregateEffect
        INTEGER,
    ospfAreaAggregateExtRouteTag
        Unsigned32
    }

ospfAreaAggregateAreaID OBJECT-TYPE
    SYNTAX      AreaID
    MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "The area within which the address aggregate is to be
         found."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
    ::= { ospfAreaAggregateEntry 1 }

ospfAreaAggregateLsdbType OBJECT-TYPE
    SYNTAX      INTEGER {
                  summaryLink (3),
                  nssaExternalLink (7)
                }
    MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "The type of the address aggregate. This field
         specifies the Lsdb type that this address
         aggregate applies to."
    REFERENCE
        "OSPF Version 2, Appendix A.4.1 The Link State
         Advertisement header"
    ::= { ospfAreaAggregateEntry 2 }

ospfAreaAggregateNet OBJECT-TYPE
    SYNTAX      IpAddress
    MAX-ACCESS  read-only -- read-only since originally an
                  -- SMIv1 index
    STATUS      current
    DESCRIPTION
        "The IP address of the net or subnet indicated
         by the range."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
    ::= { ospfAreaAggregateEntry 3 }

```

```

ospfAreaAggregateMask OBJECT-TYPE
  SYNTAX      IpAddress
  MAX-ACCESS  read-only -- read-only since originally an
                -- SMIv1 index
  STATUS      current
  DESCRIPTION
    "The subnet mask that pertains to the net or
     subnet."
  REFERENCE
    "OSPF Version 2, Appendix C.2 Area parameters"
  ::= { ospfAreaAggregateEntry 4 }

ospfAreaAggregateStatus OBJECT-TYPE
  SYNTAX      RowStatus
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "This object permits management of the table by
     facilitating actions such as row creation,
     construction, and destruction.

    The value of this object has no effect on
    whether other objects in this conceptual row can be
    modified."
  ::= { ospfAreaAggregateEntry 5 }

ospfAreaAggregateEffect OBJECT-TYPE
  SYNTAX      INTEGER {
                advertiseMatching (1),
                doNotAdvertiseMatching (2)
              }
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "Subnets subsumed by ranges either trigger the
     advertisement of the indicated aggregate
     (advertiseMatching) or result in the subnet's not
     being advertised at all outside the area."
  DEFVAL { advertiseMatching }
  ::= { ospfAreaAggregateEntry 6 }

ospfAreaAggregateExtRouteTag OBJECT-TYPE
  SYNTAX      Unsigned32
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION
    "External route tag to be included in NSSA (type-7)
     LSAs."

```

```

DEFVAL { 0 }
 ::= { ospfAreaAggregateEntry 7 }

-- OSPF Link State Database, link-local for non-virtual links

ospfLocalLsdbTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfLocalLsdbEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The OSPF Process's link-local link state database
         for non-virtual links.
        This table is identical to the OSPF LSDB Table
         in format, but contains only link-local Link State
         Advertisements for non-virtual links. The purpose is
         to allow link-local LSAs to be displayed for each
         non-virtual interface. This table is implemented to
         support type-9 LSAs that are defined
         in 'The OSPF Opaque LSA Option'."
    REFERENCE
        "OSPF Version 2, Section 12 Link State Advertisements
         and The OSPF Opaque LSA Option"
    ::= { ospf 17 }

ospfLocalLsdbEntry OBJECT-TYPE
    SYNTAX      OspfLocalLsdbEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "A single link state advertisement."
    INDEX { ospfLocalLsdbIpAddress, ospfLocalLsdbAddressLessIf,
             ospfLocalLsdbType, ospfLocalLsdbLsid, ospfLocalLsdbRouterId
         }
    ::= { ospfLocalLsdbTable 1 }

OspfLocalLsdbEntry ::=
    SEQUENCE {
        ospfLocalLsdbIpAddress
            InetAddress,
        ospfLocalLsdbAddressLessIf
            InterfaceIndexOrZero,
        ospfLocalLsdbType
            INTEGER,
        ospfLocalLsdbLsid
            InetAddress,
        ospfLocalLsdbRouterId
            RouterID,
    }

```

```

ospfLocalLsdbSequence
    Integer32,
ospfLocalLsdbAge
    Integer32,
ospfLocalLsdbChecksum
    Integer32,
ospfLocalLsdbAdvertisement
    OCTET STRING
}

ospfLocalLsdbIpAddress OBJECT-TYPE
    SYNTAX      IpAddress
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The IP address of the interface from
         which the LSA was received if the interface is
         numbered."
    REFERENCE
        "OSPF Version 2, Appendix C.3 Interface parameters"
    ::= { ospfLocalLsdbEntry 1 }

ospfLocalLsdbAddressLessIf OBJECT-TYPE
    SYNTAX      InterfaceIndexOrZero
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The interface index of the interface from
         which the LSA was received if the interface is
         unnumbered."
    REFERENCE
        "OSPF Version 2, Appendix C.3 Interface parameters"
    ::= { ospfLocalLsdbEntry 2 }

ospfLocalLsdbType OBJECT-TYPE
    SYNTAX      INTEGER { localOpaqueLink (9) }
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The type of the link state advertisement.
         Each link state type has a separate
         advertisement format."
    REFERENCE
        "OSPF Version 2, Appendix A.4.1 The Link State
         Advertisement header"
    ::= { ospfLocalLsdbEntry 3 }

ospfLocalLsdbLsid OBJECT-TYPE

```

```

SYNTAX      IpAddress
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
  "The Link State ID is an LS Type Specific field
  containing a 32-bit identifier in IP address format;
  it identifies the piece of the routing domain
  that is being described by the advertisement."
REFERENCE
  "OSPF Version 2, Section 12.1.4 Link State ID"
  ::= { ospfLocalLsdbEntry 4 }

ospfLocalLsdbRouterId OBJECT-TYPE
  SYNTAX      RouterID
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The 32-bit number that uniquely identifies the
    originating router in the Autonomous System."
REFERENCE
  "OSPF Version 2, Appendix C.1 Global parameters"
  ::= { ospfLocalLsdbEntry 5 }

ospfLocalLsdbSequence OBJECT-TYPE
  SYNTAX      Integer32
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "The sequence number field is a signed 32-bit
    integer. It starts with the value '80000001'h,
    or '-7FFFFFFF'h, and increments until '7FFFFFFF'h.
    Thus, a typical sequence number will be very negative.
    It is used to detect old and duplicate link state
    advertisements. The space of sequence numbers is linearly
    ordered. The larger the sequence number, the more recent
    the advertisement."
REFERENCE
  "OSPF Version 2, Section 12.1.6 LS sequence
  number"
  ::= { ospfLocalLsdbEntry 6 }

ospfLocalLsdbAge OBJECT-TYPE
  SYNTAX      Integer32 -- Should be 0..MaxAge, except when
                    -- doNotAge bit is set
  UNITS      "seconds"
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION

```

```

    "This field is the age of the link state
     advertisement in seconds."
REFERENCE
  "OSPF Version 2, Section 12.1.1 LS age"
 ::= { ospfLocalLsdbEntry 7 }

ospfLocalLsdbChecksum OBJECT-TYPE
  SYNTAX      Integer32
  MAX-ACCESS  read-only
  STATUS      current
DESCRIPTION
  "This field is the checksum of the complete
   contents of the advertisement, excepting the
   age field. The age field is excepted so that
   an advertisement's age can be incremented
   without updating the checksum. The checksum
   used is the same that is used for ISO
   connectionless datagrams; it is commonly referred
   to as the Fletcher checksum."
REFERENCE
  "OSPF Version 2, Section 12.1.7 LS checksum"
 ::= { ospfLocalLsdbEntry 8 }

ospfLocalLsdbAdvertisement OBJECT-TYPE
  SYNTAX      OCTET STRING (SIZE (1..65535))
  MAX-ACCESS  read-only
  STATUS      current
DESCRIPTION
  "The entire link state advertisement, including
   its header.

Note that for variable length LSAs, SNMP agents
may not be able to return the largest string size."
REFERENCE
  "OSPF Version 2, Section 12 Link State
   Advertisements"
 ::= { ospfLocalLsdbEntry 9 }

-- OSPF Link State Database, link-local for virtual Links

ospfVirtLocalLsdbTable OBJECT-TYPE
  SYNTAX      SEQUENCE OF OspfVirtLocalLsdbEntry
  MAX-ACCESS  not-accessible
  STATUS      current
DESCRIPTION
  "The OSPF Process's link-local link state database
   for virtual links.

```

This table is identical to the OSPF LSDB Table in format, but contains only link-local Link State Advertisements for virtual links. The purpose is to allow link-local LSAs to be displayed for each virtual interface. This table is implemented to support type-9 LSAs that are defined in 'The OSPF Opaque LSA Option'."

REFERENCE

"OSPF Version 2, Section 12 Link State Advertisements and The OSPF Opaque LSA Option"
 $::= \{ ospf 18 \}$

```
ospfvirtLocalLsdbEntry OBJECT-TYPE
    SYNTAX          OspfvirtLocalLsdbEntry
    MAX-ACCESS     not-accessible
    STATUS         current
    DESCRIPTION    "A single link state advertisement."
    INDEX { ospfvirtLocalLsdbTransitArea,
            ospfvirtLocalLsdbNeighbor,
            ospfvirtLocalLsdbType,
            ospfvirtLocalLsdbLsid,
            ospfvirtLocalLsdbRouterId
        }
    ::= { ospfvirtLocalLsdbTable 1 }
```

```
OspfvirtLocalLsdbEntry ::=
    SEQUENCE {
        ospfvirtLocalLsdbTransitArea
            AreaID,
        ospfvirtLocalLsdbNeighbor
            RouterID,
        ospfvirtLocalLsdbType
            INTEGER,
        ospfvirtLocalLsdbLsid
            IpAddress,
        ospfvirtLocalLsdbRouterId
            RouterID,
        ospfvirtLocalLsdbSequence
            Integer32,
        ospfvirtLocalLsdbAge
            Integer32,
        ospfvirtLocalLsdbChecksum
            Integer32,
        ospfvirtLocalLsdbAdvertisement
            OCTET STRING
    }
```

```
ospfvirtLocalLsdbTransitArea OBJECT-TYPE
```

```

SYNTAX      AreaID
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
  "The transit area that the virtual link
  traverses. By definition, this is not 0.0.0.0."
REFERENCE
  "OSPF Version 2, Appendix C.3 Interface parameters"
 ::= { ospfVirtLocalLsdbEntry 1 }

ospfVirtLocalLsdbNeighbor OBJECT-TYPE
  SYNTAX      RouterID
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The Router ID of the virtual neighbor."
REFERENCE
  "OSPF Version 2, Appendix C.3 Interface parameters"
 ::= { ospfVirtLocalLsdbEntry 2 }

ospfVirtLocalLsdbType OBJECT-TYPE
  SYNTAX      INTEGER { localOpaqueLink (9) }
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The type of the link state advertisement.
    Each link state type has a separate
    advertisement format."
REFERENCE
  "OSPF Version 2, Appendix A.4.1 The Link State
  Advertisement header"
 ::= { ospfVirtLocalLsdbEntry 3 }

ospfVirtLocalLsdbLsid OBJECT-TYPE
  SYNTAX      IpAddress
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The Link State ID is an LS Type Specific field
    containing a 32-bit identifier in IP address format;
    it identifies the piece of the routing domain
    that is being described by the advertisement."
REFERENCE
  "OSPF Version 2, Section 12.1.4 Link State ID"
 ::= { ospfVirtLocalLsdbEntry 4 }

ospfVirtLocalLsdbRouterId OBJECT-TYPE
  SYNTAX      RouterID

```

```

MAX-ACCESS    not-accessible
STATUS        current
DESCRIPTION
  "The 32-bit number that uniquely identifies the
  originating router in the Autonomous System."
REFERENCE
  "OSPF Version 2, Appendix C.1 Global parameters"
 ::= { ospfVirtLocalLsdbEntry 5 }

ospfVirtLocalLsdbSequence OBJECT-TYPE
  SYNTAX        Integer32
  MAX-ACCESS   read-only
  STATUS        current
  DESCRIPTION
    "The sequence number field is a signed 32-bit
    integer. It starts with the value '80000001'h,
    or '-7FFFFFFF'h, and increments until '7FFFFFFF'h.
    Thus, a typical sequence number will be very negative.
    It is used to detect old and duplicate link state
    advertisements. The space of sequence numbers is linearly
    ordered. The larger the sequence number, the more recent
    the advertisement."
  REFERENCE
    "OSPF Version 2, Section 12.1.6 LS sequence
     number"
 ::= { ospfVirtLocalLsdbEntry 6 }

ospfVirtLocalLsdbAge OBJECT-TYPE
  SYNTAX        Integer32 -- Should be 0..MaxAge, except when
                        -- doNotAge bit is set
  UNITS         "seconds"
  MAX-ACCESS   read-only
  STATUS        current
  DESCRIPTION
    "This field is the age of the link state
     advertisement in seconds."
  REFERENCE
    "OSPF Version 2, Section 12.1.1 LS age"
 ::= { ospfVirtLocalLsdbEntry 7 }

ospfVirtLocalLsdbChecksum OBJECT-TYPE
  SYNTAX        Integer32
  MAX-ACCESS   read-only
  STATUS        current
  DESCRIPTION
    "This field is the checksum of the complete
     contents of the advertisement, excepting the
     age field. The age field is excepted so that

```

an advertisement's age can be incremented without updating the checksum. The checksum used is the same that is used for ISO connectionless datagrams; it is commonly referred to as the Fletcher checksum."

REFERENCE

"OSPF Version 2, Section 12.1.7 LS checksum"
 ::= { ospfVirtLocalLsdbEntry 8 }

ospfVirtLocalLsdbAdvertisement OBJECT-TYPE
 SYNTAX OCTET STRING (SIZE (1..65535))
 MAX-ACCESS read-only
 STATUS current
DESCRIPTION
 "The entire link state advertisement, including its header."
REFERENCE
 "OSPF Version 2, Section 12 Link State Advertisements.
 Note that for variable length LSAs, SNMP agents may not be able to return the largest string size."
 ::= { ospfVirtLocalLsdbEntry 9 }

-- OSPF Link State Database, AS-scope

ospfAsLsdbTable OBJECT-TYPE
 SYNTAX SEQUENCE OF OspfAsLsdbEntry
 MAX-ACCESS not-accessible
 STATUS current
DESCRIPTION
 "The OSPF Process's AS-scope LSA link state database. The database contains the AS-scope Link State Advertisements from throughout the areas that the device is attached to.

This table is identical to the OSPF LSDB Table in format, but contains only AS-scope Link State Advertisements. The purpose is to allow AS-scope LSAs to be displayed once for the router rather than once in each non-stub area."

REFERENCE

"OSPF Version 2, Section 12 Link State Advertisements"
 ::= { ospf 19 }

ospfAsLsdbEntry OBJECT-TYPE
 SYNTAX OspfAsLsdbEntry

```

MAX-ACCESS    not-accessible
STATUS        current
DESCRIPTION
  "A single link state advertisement."
INDEX { ospfAsLsdbType, ospfAsLsdbLsid, ospfAsLsdbRouterId }
::= { ospfAsLsdbTable 1 }

OspfAsLsdbEntry ::= 
SEQUENCE {
  ospfAsLsdbType
    INTEGER,
  ospfAsLsdbLsid
    IpAddress,
  ospfAsLsdbRouterId
    RouterID,
  ospfAsLsdbSequence
    Integer32,
  ospfAsLsdbAge
    Integer32,
  ospfAsLsdbChecksum
    Integer32,
  ospfAsLsdbAdvertisement
    OCTET STRING
}

ospfAsLsdbType OBJECT-TYPE
SYNTAX      INTEGER {
            asExternalLink (5),
            asOpaqueLink   (11)
            }
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
  "The type of the link state advertisement.
  Each link state type has a separate
  advertisement format."
REFERENCE
  "OSPF Version 2, Appendix A.4.1 The Link State
  Advertisement header"
::= { ospfAsLsdbEntry 1 }

ospfAsLsdbLsid OBJECT-TYPE
SYNTAX      IpAddress
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
  "The Link State ID is an LS Type Specific field
  containing either a Router ID or an IP address;

```

it identifies the piece of the routing domain
that is being described by the advertisement."

REFERENCE
 "OSPF Version 2, Section 12.1.4 Link State ID"
 $::= \{ \text{ospfAsLsdbEntry} \ 2 \ }$

ospfAsLsdbRouterId OBJECT-TYPE
 SYNTAX RouterID
 MAX-ACCESS not-accessible
 STATUS current
DESCRIPTION
 "The 32-bit number that uniquely identifies the
originating router in the Autonomous System."

REFERENCE
 "OSPF Version 2, Appendix C.1 Global parameters"
 $::= \{ \text{ospfAsLsdbEntry} \ 3 \ }$

ospfAsLsdbSequence OBJECT-TYPE
 SYNTAX Integer32
 MAX-ACCESS read-only
 STATUS current
DESCRIPTION
 "The sequence number field is a signed 32-bit
integer. It starts with the value '80000001'h,
or '-7FFFFFFF'h, and increments until '7FFFFFFF'h.
Thus, a typical sequence number will be very negative.
It is used to detect old and duplicate link state
advertisements. The space of sequence numbers is linearly
ordered. The larger the sequence number, the more recent
the advertisement."

REFERENCE
 "OSPF Version 2, Section 12.1.6 LS sequence
number"
 $::= \{ \text{ospfAsLsdbEntry} \ 4 \ }$

ospfAsLsdbAge OBJECT-TYPE
 SYNTAX Integer32 -- Should be 0..MaxAge, except when
 -- doNotAge bit is set
 UNITS "seconds"
 MAX-ACCESS read-only
 STATUS current
DESCRIPTION
 "This field is the age of the link state
advertisement in seconds."

REFERENCE
 "OSPF Version 2, Section 12.1.1 LS age"
 $::= \{ \text{ospfAsLsdbEntry} \ 5 \ }$

```

ospfAsLsdbChecksum OBJECT-TYPE
  SYNTAX      Integer32
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "This field is the checksum of the complete
     contents of the advertisement, excepting the
     age field. The age field is excepted so that
     an advertisement's age can be incremented
     without updating the checksum. The checksum
     used is the same that is used for ISO
     connectionless datagrams; it is commonly referred
     to as the Fletcher checksum."
  REFERENCE
    "OSPF Version 2, Section 12.1.7 LS checksum"
  ::= { ospfAsLsdbEntry 6 }

ospfAsLsdbAdvertisement OBJECT-TYPE
  SYNTAX      OCTET STRING (SIZE (1..65535))
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "The entire link state advertisement, including
     its header."
  REFERENCE
    "OSPF Version 2, Section 12 Link State
     Advertisements.

     Note that for variable length LSAs, SNMP agents
     may not be able to return the largest string size."
  ::= { ospfAsLsdbEntry 7 }

-- OSPF Area LSA Counter Table

ospfAreaLsaCountTable OBJECT-TYPE
  SYNTAX      SEQUENCE OF OspfAreaLsaCountEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "This table maintains per-area, per-LSA-type counters"
  ::= { ospf 20 }

ospfAreaLsaCountEntry OBJECT-TYPE
  SYNTAX      OspfAreaLsaCountEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "An entry with a number of link advertisements

```

```

        of a given type for a given area."
INDEX { ospfAreaLsaCountAreaId, ospfAreaLsaCountLsaType }
::= { ospfAreaLsaCountTable 1 }

OspfAreaLsaCountEntry ::=

SEQUENCE {
    ospfAreaLsaCountAreaId
        AreaID,
    ospfAreaLsaCountLsaType
        INTEGER,
    ospfAreaLsaCountNumber
        Gauge32
}
}

ospfAreaLsaCountAreaId OBJECT-TYPE
SYNTAX      AreaID
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "This entry Area ID."
::= { ospfAreaLsaCountEntry 1 }

ospfAreaLsaCountLsaType OBJECT-TYPE
SYNTAX      INTEGER {
    routerLink (1),
    networkLink (2),
    summaryLink (3),
    asSummaryLink (4),
    multicastLink (6),
    nssaExternalLink (7),
    areaOpaqueLink (10)
}
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "This entry LSA type."
::= { ospfAreaLsaCountEntry 2 }

ospfAreaLsaCountNumber OBJECT-TYPE
SYNTAX      Gauge32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "Number of LSAs of a given type for a given area."
::= { ospfAreaLsaCountEntry 3 }

-- conformance information

```

```
ospfConformance OBJECT IDENTIFIER ::= { ospf 15 }

ospfGroups      OBJECT IDENTIFIER ::= { ospfConformance 1 }
ospfCompliances OBJECT IDENTIFIER ::= { ospfConformance 2 }

-- compliance statements

ospfCompliance MODULE-COMPLIANCE
    STATUS      deprecated
    DESCRIPTION
        "The compliance statement for OSPF systems
         conforming to RFC 1850."
    MODULE      -- this module
    MANDATORY-GROUPS {
        ospfBasicGroup,
        ospfAreaGroup,
        ospfStubAreaGroup,
        ospfIfGroup,
        ospfIfMetricGroup,
        ospfVirtIfGroup,
        ospfNbrGroup,
        ospfVirtNbrGroup,
        ospfAreaAggregateGroup
    }
    GROUP  ospfHostGroup
    DESCRIPTION
        "This group is mandatory for OSPF systems that support
         attached hosts."
    GROUP  ospfLsdbGroup
    DESCRIPTION
        "This group is mandatory for OSPF systems that display
         their per-area link state database."
    GROUP  ospfExtLsdbGroup
    DESCRIPTION
        "This group is mandatory for OSPF systems that display
         their external link state database."
 ::= { ospfCompliances 1 }

ospfCompliance2 MODULE-COMPLIANCE
    STATUS      current
    DESCRIPTION
        "The compliance statement."
    MODULE      -- this module
    MANDATORY-GROUPS {
        ospfBasicGroup2,
        ospfAreaGroup2,
        ospfStubAreaGroup,
        ospfIfGroup2,
```

```

    ospfIfMetricGroup,
    ospfVirtIfGroup2,
    ospfNbrGroup2,
    ospfVirtNbrGroup2,
    ospfAreaAggregateGroup2
}
GROUP  ospfHostGroup2
DESCRIPTION
    "This group is mandatory for OSPF systems that support
     attached hosts."
GROUP  ospfLsdbGroup
DESCRIPTION
    "This group is mandatory for OSPF systems that display
     their per-area link state database."
GROUP  ospfAsLsdbGroup
DESCRIPTION
    "This group is mandatory for OSPF systems that display
     their AS-scope link state database."
GROUP  ospfLocalLsdbGroup
DESCRIPTION
    "This group is mandatory for OSPF systems that display
     their per-link link state database for non-virtual
     links."
GROUP  ospfVirtLocalLsdbGroup
DESCRIPTION
    "This group is mandatory for OSPF systems that display
     their per-link link state database for virtual links."
GROUP  ospfAreaLsaCountGroup
DESCRIPTION
    "This group is mandatory for OSPF systems that display
     per-area, per-LSA-type counters."
 ::= { ospfCompliances 2 }

ospfComplianceObsolete MODULE-COMPLIANCE
    STATUS      obsolete
    DESCRIPTION
        "Contains obsolete object groups."
    MODULE      -- this module
GROUP  ospfAreaRangeGroup
DESCRIPTION
    "This group is obsolete, and it is mandatory only
     for non-Classless Inter-Domain Routing (CIDR) OSPF
     systems that support multiple areas."
GROUP  ospfObsoleteGroup
DESCRIPTION
    "This group contains obsolete objects,
     which are no longer required for OSPF systems."
 ::= { ospfCompliances 3 }

```

-- units of conformance

```
ospfBasicGroup      OBJECT-GROUP
  OBJECTS {
    ospfRouterId,
    ospfAdminStat,
    ospfVersionNumber,
    ospfAreaBdrRtrStatus,
    ospfASBdrRtrStatus,
    ospfExternLsaCount,
    ospfExternLsaCksumSum,
    ospfTOSSupport,
    ospfOriginateNewLsas,
    ospfRxNewLsas,
    ospfExtLsdbLimit,
    ospfMulticastExtensions,
    ospfExitOverflowInterval,
    ospfDemandExtensions
  }
  STATUS      deprecated
  DESCRIPTION
    "These objects are used to monitor/manage
     global OSPF parameters. This object group
     conforms to RFC 1850."
 ::= { ospfGroups 1 }
```

```
ospfAreaGroup      OBJECT-GROUP
  OBJECTS {
    ospfAreaId,
    ospfImportAsExtern,
    ospfSpfRuns,
    ospfAreaBdrRtrCount,
    ospfAsBdrRtrCount,
    ospfAreaLsaCount,
    ospfAreaLsaCksumSum,
    ospfAreaSummary,
    ospfAreaStatus
  }
  STATUS      deprecated
  DESCRIPTION
    "These objects are used for OSPF systems
     supporting areas per RFC 1850."
 ::= { ospfGroups 2 }
```

```
ospfStubAreaGroup   OBJECT-GROUP
  OBJECTS {
    ospfStubAreaId,
    ospfStubTOS,
```

```
    ospfStubMetric,
    ospfStubStatus,
    ospfStubMetricType
}
STATUS      current
DESCRIPTION
  "These objects are used for OSPF systems
   supporting stub areas."
 ::= { ospfGroups 3 }

ospfLsdbGroup      OBJECT-GROUP
OBJECTS {
    ospfLsdbAreaId,
    ospfLsdbType,
    ospfLsdbLsid,
    ospfLsdbRouterId,
    ospfLsdbSequence,
    ospfLsdbAge,
    ospfLsdbChecksum,
    ospfLsdbAdvertisement
}
STATUS      current
DESCRIPTION
  "These objects are used for OSPF systems
   that display their link state database."
 ::= { ospfGroups 4 }

ospfAreaRangeGroup      OBJECT-GROUP
OBJECTS {
    ospfAreaRangeAreaId,
    ospfAreaRangeNet,
    ospfAreaRangeMask,
    ospfAreaRangeStatus,
    ospfAreaRangeEffect
}
STATUS      obsolete
DESCRIPTION
  "These objects are used for non-CIDR OSPF
   systems that support multiple areas.  This
   object group is obsolete."
 ::= { ospfGroups 5 }

ospfHostGroup      OBJECT-GROUP
OBJECTS {
    ospfHostIpAddress,
    ospfHostTOS,
    ospfHostMetric,
    ospfHostStatus,
```

```
    ospfHostAreaID
  }
STATUS      deprecated
DESCRIPTION
  "These objects are used for OSPF systems
   that support attached hosts."
 ::= { ospfGroups 6 }

ospfIfGroup      OBJECT-GROUP
OBJECTS {
  ospfIfIpAddress,
  ospfAddressLessIf,
  ospfIfAreaId,
  ospfIfType,
  ospfIfAdminStat,
  ospfIfRtrPriority,
  ospfIfTransitDelay,
  ospfIfRetransInterval,
  ospfIfHelloInterval,
  ospfIfRtrDeadInterval,
  ospfIfPollInterval,
  ospfIfState,
  ospfIfDesignatedRouter,
  ospfIfBackupDesignatedRouter,
  ospfIfEvents,
  ospfIfAuthType,
  ospfIfAuthKey,
  ospfIfStatus,
  ospfIfMulticastForwarding,
  ospfIfDemand
}
STATUS      deprecated
DESCRIPTION
  "These objects are used to monitor/manage OSPF
   interfaces. This object group conforms to RFC 1850."
 ::= { ospfGroups 7 }

ospfIfMetricGroup      OBJECT-GROUP
OBJECTS {
  ospfIfMetricIpAddress,
  ospfIfMetricAddressLessIf,
  ospfIfMetricTOS,
  ospfIfMetricValue,
  ospfIfMetricStatus
}
STATUS      current
DESCRIPTION
  "These objects are used for OSPF systems for supporting
```

```
    interface metrics."
 ::= { ospfGroups 8 }

ospfVirtIfGroup      OBJECT-GROUP
OBJECTS {
  ospfVirtIfAreaId,
  ospfVirtIfNeighbor,
  ospfVirtIfTransitDelay,
  ospfVirtIfRetransInterval,
  ospfVirtIfHelloInterval,
  ospfVirtIfRtrDeadInterval,
  ospfVirtIfState,
  ospfVirtIfEvents,
  ospfVirtIfAuthType,
  ospfVirtIfAuthKey,
  ospfVirtIfStatus
}
STATUS      deprecated
DESCRIPTION
  "These objects are used for OSPF systems for supporting
  virtual interfaces. This object group conforms
  to RFC 1850."
 ::= { ospfGroups 9 }

ospfNbrGroup      OBJECT-GROUP
OBJECTS {
  ospfNbrIpAddr,
  ospfNbrAddressLessIndex,
  ospfNbrRtrId,
  ospfNbrOptions,
  ospfNbrPriority,
  ospfNbrState,
  ospfNbrEvents,
  ospfNbrLsRetransQLen,
  ospfNbmaNbrStatus,
  ospfNbmaNbrPermanence,
  ospfNbrHelloSuppressed
}
STATUS      deprecated
DESCRIPTION
  "These objects are used to monitor/manage OSPF neighbors.
  This object group conforms to RFC 1850."
 ::= { ospfGroups 10 }

ospfVirtNbrGroup      OBJECT-GROUP
OBJECTS {
  ospfVirtNbrArea,
  ospfVirtNbrRtrId,
```

```
    ospfVirtNbrIpAddr,
    ospfVirtNbrOptions,
    ospfVirtNbrState,
    ospfVirtNbrEvents,
    ospfVirtNbrLsRetransQLen,
    ospfVirtNbrHelloSuppressed
}
STATUS      deprecated
DESCRIPTION
  "These objects are used to monitor/manage OSPF virtual
neighbors. This object group conforms to RFC 1850."
::= { ospfGroups 11 }

ospfExtLsdbGroup      OBJECT-GROUP
OBJECTS {
    ospfExtLsdbType,
    ospfExtLsdbLsid,
    ospfExtLsdbRouterId,
    ospfExtLsdbSequence,
    ospfExtLsdbAge,
    ospfExtLsdbChecksum,
    ospfExtLsdbAdvertisement
}
STATUS      deprecated
DESCRIPTION
  "These objects are used for OSPF systems that display
their link state database. This object group
conforms to RFC 1850.

This object group is replaced by the ospfAsLsdbGroup
in order to support any AS-scope LSA type in a single
table."
::= { ospfGroups 12 }

ospfAreaAggregateGroup      OBJECT-GROUP
OBJECTS {
    ospfAreaAggregateAreaID,
    ospfAreaAggregateLsdbType,
    ospfAreaAggregateNet,
    ospfAreaAggregateMask,
    ospfAreaAggregateStatus,
    ospfAreaAggregateEffect
}
STATUS      deprecated
DESCRIPTION
  "These objects are used for OSPF systems to support
network prefix aggregation across areas."
```

```
 ::= { ospfGroups 13 }

ospfLocalLsdbGroup      OBJECT-GROUP
OBJECTS {
    ospfLocalLsdbSequence,
    ospfLocalLsdbAge,
    ospfLocalLsdbChecksum,
    ospfLocalLsdbAdvertisement
}
STATUS      current
DESCRIPTION
    "These objects are used for OSPF systems
     that display their link-local link state databases
     for non-virtual links."
 ::= { ospfGroups 14 }

ospfVirtLocalLsdbGroup      OBJECT-GROUP
OBJECTS {
    ospfVirtLocalLsdbSequence,
    ospfVirtLocalLsdbAge,
    ospfVirtLocalLsdbChecksum,
    ospfVirtLocalLsdbAdvertisement
}
STATUS      current
DESCRIPTION
    "These objects are used for OSPF systems
     that display their link-local link state databases
     for virtual links."
 ::= { ospfGroups 15 }

ospfAsLsdbGroup      OBJECT-GROUP
OBJECTS {
    ospfAsLsdbSequence,
    ospfAsLsdbAge,
    ospfAsLsdbChecksum,
    ospfAsLsdbAdvertisement
}
STATUS      current
DESCRIPTION
    "These objects are used for OSPF systems
     that display their AS-scope link state database."
 ::= { ospfGroups 16 }

ospfBasicGroup2      OBJECT-GROUP
OBJECTS {
    ospfRouterId,
    ospfAdminStat,
    ospfVersionNumber,
```

```
        ospfAreaBdrRtrStatus,
        ospfASBdrRtrStatus,
        ospfExternLsaCount,
        ospfExternLsaCksumSum,
        ospfTOSSupport,
        ospfOriginateNewLsas,
        ospfRxNewLsas,
        ospfExtLsdbLimit,
        ospfMulticastExtensions,
        ospfExitOverflowInterval,
        ospfDemandExtensions,
        ospfRFC1583Compatibility,
        ospfOpaqueLsaSupport,
        ospfReferenceBandwidth,
        ospfRestartSupport,
        ospfRestartInterval,
        ospfRestartStrictLsaChecking,
        ospfRestartStatus,
        ospfRestartAge,
        ospfRestartExitReason,
        ospfAsLsaCount,
        ospfAsLsaCksumSum,
        ospfStubRouterSupport,
        ospfStubRouterAdvertisement,
        ospfDiscontinuityTime
    }
STATUS      current
DESCRIPTION
    "These objects are used to monitor/manage OSPF global
     parameters."
 ::= { ospfGroups 17 }

ospfAreaGroup2      OBJECT-GROUP
OBJECTS {
    ospfAreaId,
    ospfImportAsExtern,
    ospfSpfRuns,
    ospfAreaBdrRtrCount,
    ospfAsBdrRtrCount,
    ospfAreaLsaCount,
    ospfAreaLsaCksumSum,
    ospfAreaSummary,
    ospfAreaStatus,
    ospfAreaNssaTranslatorRole,
    ospfAreaNssaTranslatorState,
    ospfAreaNssaTranslatorStabilityInterval,
    ospfAreaNssaTranslatorEvents
}
```

```
STATUS      current
DESCRIPTION
    "These objects are used by OSPF systems
     to support areas."
 ::= { ospfGroups 18 }

ospfIfGroup2   OBJECT-GROUP
 OBJECTS {
    ospfIfIpAddress,
    ospfAddressLessIf,
    ospfIfAreaId,
    ospfIfType,
    ospfIfAdminStat,
    ospfIfRtrPriority,
    ospfIfTransitDelay,
    ospfIfRetransInterval,
    ospfIfHelloInterval,
    ospfIfRtrDeadInterval,
    ospfIfPollInterval,
    ospfIfState,
    ospfIfDesignatedRouter,
    ospfIfBackupDesignatedRouter,
    ospfIfEvents,
    ospfIfAuthType,
    ospfIfAuthKey,
    ospfIfStatus,
    ospfIfMulticastForwarding,
    ospfIfDemand,
    ospfIfLsaCount,
    ospfIfLsaCksumSum
 }
STATUS      current
DESCRIPTION
    "These objects are used to monitor/manage OSPF interfaces."
 ::= { ospfGroups 19 }

ospfVirtIfGroup2   OBJECT-GROUP
 OBJECTS {
    ospfVirtIfAreaId,
    ospfVirtIfNeighbor,
    ospfVirtIfTransitDelay,
    ospfVirtIfRetransInterval,
    ospfVirtIfHelloInterval,
    ospfVirtIfRtrDeadInterval,
    ospfVirtIfState,
    ospfVirtIfEvents,
    ospfVirtIfAuthType,
    ospfVirtIfAuthKey,
```

```
    ospfVirtIfStatus,
    ospfVirtIfLsaCount,
    ospfVirtIfLsaCksumSum,
    ospfIfDesignatedRouterId,
    ospfIfBackupDesignatedRouterId
}
STATUS      current
DESCRIPTION
    "These objects are used to monitor/manage OSPF
     virtual interfaces."
::= { ospfGroups 20 }

ospfNbrGroup2      OBJECT-GROUP
OBJECTS {
    ospfNbrIpAddr,
    ospfNbrAddressLessIndex,
    ospfNbrRtrId,
    ospfNbrOptions,
    ospfNbrPriority,
    ospfNbrState,
    ospfNbrEvents,
    ospfNbrLsRetransQLen,
    ospfNbmaNbrStatus,
    ospfNbmaNbrPermanence,
    ospfNbrHelloSuppressed,
    ospfNbrRestartHelperStatus,
    ospfNbrRestartHelperAge,
    ospfNbrRestartHelperExitReason
}
STATUS      current
DESCRIPTION
    "These objects are used to monitor/manage OSPF
     neighbors."
::= { ospfGroups 21 }

ospfVirtNbrGroup2      OBJECT-GROUP
OBJECTS {
    ospfVirtNbrArea,
    ospfVirtNbrRtrId,
    ospfVirtNbrIpAddr,
    ospfVirtNbrOptions,
    ospfVirtNbrState,
    ospfVirtNbrEvents,
    ospfVirtNbrLsRetransQLen,
    ospfVirtNbrHelloSuppressed,
    ospfVirtNbrRestartHelperStatus,
    ospfVirtNbrRestartHelperAge,
    ospfVirtNbrRestartHelperExitReason
```

```
        }
STATUS      current
DESCRIPTION
  "These objects are used to monitor/manage OSPF
  virtual neighbors."
 ::= { ospfGroups 22 }

ospfAreaAggregateGroup2      OBJECT-GROUP
  OBJECTS {
    ospfAreaAggregateAreaID,
    ospfAreaAggregateLsdbType,
    ospfAreaAggregateNet,
    ospfAreaAggregateMask,
    ospfAreaAggregateStatus,
    ospfAreaAggregateEffect,
    ospfAreaAggregateExtRouteTag
  }
STATUS      current
DESCRIPTION
  "These objects are used for OSPF systems to support
  network prefix aggregation across areas."
 ::= { ospfGroups 23 }

ospfAreaLsaCountGroup      OBJECT-GROUP
  OBJECTS {
    ospfAreaLsaCountNumber
  }
STATUS      current
DESCRIPTION
  "These objects are used for OSPF systems that display
  per-area, per-LSA-type counters."
 ::= { ospfGroups 24 }

ospfHostGroup2      OBJECT-GROUP
  OBJECTS {
    ospfHostIpAddress,
    ospfHostTOS,
    ospfHostMetric,
    ospfHostStatus,
    ospfHostCfgAreaID
  }
STATUS      current
DESCRIPTION
  "These objects are used for OSPF systems
  that support attached hosts."
 ::= { ospfGroups 25 }

-- This object group is included for SMI conformance. It is not a
```

```
-- mandatory group for compliance with this MIB

ospfObsoleteGroup      OBJECT-GROUP
  OBJECTS {
    ospfAuthType
  }
  STATUS      obsolete
  DESCRIPTION
    "These objects are obsolete and are no longer required for
     OSPF systems. They are placed into this group for SMI
     conformance."
 ::= { ospfGroups 26 }
```

END

4. OSPF Trap Overview

4.1. Introduction

OSPF is an event-driven routing protocol, where an event can be a change in an OSPF interface's link-level status, the expiration of an OSPF timer, or the reception of an OSPF protocol packet. Many of the actions that OSPF takes as a result of these events will result in a change of the routing topology.

As routing topologies become large and complex, it is often difficult to locate the source of a topology change or unpredicted routing path by polling a large number of routers. Because of the difficulty of polling a large number of devices, a more prudent approach is for devices to notify a network manager of potentially critical OSPF events using SNMP traps.

This section defines a set of traps, objects, and mechanisms to enhance the ability to manage IP internetworks that use OSPF as their Interior Gateway Protocol (IGP). It is an optional but very useful extension to the OSPF MIB.

4.2. Approach

The mechanism for sending traps is straightforward. When an exception event occurs, the application notifies the local agent, who sends a trap to the appropriate SNMP management stations. The message includes the trap type and may include a list of trap-specific variables. Section 5 gives the trap definitions, which includes the variable lists. The Router ID of the originator of the trap is included in the variable list so that the network manager may easily determine the source of the trap.

To limit the frequency of OSPF traps, the following additional mechanisms are suggested.

4.3. Ignoring Initial Activity

The majority of critical events occur when OSPF is enabled on a router, at which time the designated router is elected and neighbor adjacencies are formed. During this initial period, a potential flood of traps is unnecessary since the events are expected. To avoid unnecessary traps, a router should not originate expected OSPF interface-related traps until two of that interface's dead timer intervals have elapsed. The expected OSPF interface traps are ospfIfStateChange, ospfVirtIfStateChange, ospfNbrStateChange, ospfVirtNbrStateChange, ospfTxRetransmit, and ospfVirtIfTxRetransmit. Additionally, ospfMaxAgeLsa and ospfOriginateLsa traps should not be originated until two dead timer intervals have elapsed where the dead timer interval used should be the dead timer with the smallest value.

4.4. Throttling Traps

The mechanism for throttling the traps is similar to the mechanism explained in RFC 1224 [RFC1224]. The basic premise of the throttling mechanism is that of a sliding window, defined in seconds and an upper bound on the number of traps that may be generated within this window. Note that unlike RFC 1224, traps are not sent to inform the network manager that the throttling mechanism has kicked in.

A single window should be used to throttle all OSPF trap types except for the ospfLsdbOverflow and the ospfLsdbApproachingOverflow traps, which should not be throttled. For example, with a window time of 3, an upper bound of 3, and events to cause trap types 1, 3, 5, and 7 (4 traps within a 3-second period), the type-7 (the 4th) trap should not be generated.

Appropriate values are 7 traps with a window time of 10 seconds.

4.5. One Trap Per OSPF Event

Several of the traps defined in section 5 are generated as the result of finding an unusual condition while parsing an OSPF packet or a processing a timer event. There may be more than one unusual condition detected while handling the event. For example, a link state update packet may contain several retransmitted link state advertisements (LSAs), or a retransmitted database description packet may contain several database description entries. To limit the number of traps and variables, OSPF should generate at most one trap per OSPF event. Only the variables associated with the first unusual condition should be included with the trap. Similarly, if more than one type of unusual condition is encountered while parsing the packet, only the first event will generate a trap.

4.6. Polling Event Counters

Many of the tables in the OSPF MIB contain generalized event counters. By enabling the traps defined in this document, a network manager can obtain more specific information about these events. A network manager may want to poll these event counters and enable specific OSPF traps when a particular counter starts increasing abnormally.

The following table shows the relationship between the event counters defined in the OSPF MIB and the trap types.

Counter32	Trap Type
ospfOriginateNewLsas	ospfOriginateLsa
ospfIfEvents	ospfIfStateChange ospfConfigError ospfIfAuthFailure ospfRxBadPacket ospfTxRetransmit
ospfvirtIfEvents	ospfvirtIfStateChange ospfvirtIfConfigError ospfvirtIfAuthFailure ospfvirtIfRxBadPacket ospfvirtIfTxRetransmit
ospfnbrEvents	ospfnbrStateChange
ospfvirtNbrEvents	ospfvirtNbrStateChange
ospfExternLSACount	ospflsdbApproachingOverflow
ospfExternLSACount	ospflsdbOverflow

4.7. Translating Notification Parameters

The definition of the OSPF notifications pre-dates the RFC 2578 [RFC2578] requirement of having a zero value for the penultimate sub-identifier for translating SNMPv2/SNMPv3 trap parameters to SNMPv1 trap parameters. RFC 3584 [RFC3584], section 3, defines the translation rules that can be implemented by intermediate proxy-agents or multi-lingual agents to convert SNMPv2/SNMPv3 notifications to SNMPv1 notifications and vice versa. The conversion is not reversible, that is, a conversion to one SNMP version and then back again will result in an incorrectly formatted version of the notification.

According to the rules specified in RFC 3584, section 3.1, translation of OSPF notifications from SNMPv1 to SNMPv2/SNMPv3 would result in the SNMPv2/SNMPv3 snmpTrapOID being the concatenation of the SNMPv1 'enterprise' parameter and two additional sub-identifiers, '0' and the SNMPv1 'specific-trap' parameter.

According to the rules specified in RFC 3584, section 3.2, translation of OSPF notifications from SNMPv2/SNMPv3 to SNMPv1, as the notifications are defined in this MIB, would result in the SNMPv1 'enterprise' parameter being set to the SNMPv2/SNMPv3 snmpTrapOID parameter value with the last sub-identifier removed and the 'specific-trap' parameter being set to the last sub-identifier of the SNMPv2/SNMPv3 snmpTrapOID parameter.

Note that a notification originated from an SNMPv1 agent will not be converted into the same notification that would be originated from a native SNMPv2/SNMPv3 agent.

4.8. Historical Artifacts

The MIB modules that are updated by this document were originally written in SMIv1 for SNMPv1 when only traps were used. Since this version of the MIB module is written in SMIv2, it should be understood that all types of notifications, trap and inform PDUs, may be used by native SNMPv2 and SNMPv3 agents, although only traps are mentioned. Also, for backwards compatibility, the OSPF Trap module remains rooted at {ospf 16}.

5. OSPF Trap Definitions

```
OSPF-TRAP-MIB DEFINITIONS ::= BEGIN
```

```
IMPORTS
```

```
    MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE, IpAddress  
        FROM SNMPv2-SMI  
    MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP  
        FROM SNMPv2-CONF  
    ospfRouterId, ospfIfIpAddress, ospfAddressLessIf, ospfIfState,  
    ospfVirtIfAreaId, ospfVirtIfNeighbor, ospfVirtIfState,  
    ospfNbrIpAddress, ospfNbrAddressLessIndex, ospfNbrRtrId,  
    ospfNbrState, ospfVirtNbrArea, ospfVirtNbrRtrId,  
    ospfVirtNbrState, ospfLsdbType, ospfLsdbLsid, ospfLsdbRouterId,  
    ospfLsdbAreaId, ospfExtLsdbLimit, ospf, ospfAreaId,  
    ospfAreaNssaTranslatorState, ospfRestartStatus,  
    ospfRestartInterval, ospfRestartExitReason,  
    ospfNbrRestartHelperStatus, ospfNbrRestartHelperAge,  
    ospfNbrRestartHelperExitReason, ospfVirtNbrRestartHelperStatus,  
    ospfVirtNbrRestartHelperAge, ospfVirtNbrRestartHelperExitReason  
        FROM OSPF-MIB;
```

```
ospfTrap MODULE-IDENTITY
```

```
LAST-UPDATED "200611100000Z" -- November 10, 2006 00:00:00 EST  
ORGANIZATION "IETF OSPF Working Group"
```

```
CONTACT-INFO
```

```
"WG E-Mail: ospf@ietf.org
```

```
WG Chairs: acee@cisco.com  
            rohit@gmail.com
```

```
Editors: Dan Joyal  
        Nortel  
        600 Technology Park Drive  
        Billerica, MA 01821  
        djoyal@nortel.com
```

```
Piotr Galecki  
Airvana  
19 Alpha Road  
Chelmsford, MA 01824  
pgalecki@airvana.com
```

```
Spencer Giacalone  
CSFB  
Eleven Madison Ave  
New York, NY 10010-3629
```

spencer.giacalone@gmail.com"

DESCRIPTION

"The MIB module to describe traps for the OSPF Version 2 Protocol.

Copyright (C) The IETF Trust (2006).
This version of this MIB module is part of
RFC 4750; see the RFC itself for full legal
notices."

REVISION "200611100000Z" -- November 10, 2006 00:00:00 EST
DESCRIPTION

"Updated for latest changes to OSPFv2:
-added graceful restart related traps
-added new config error types
-added ospfNssaTranslatorStatusChange trap.
See Appendix B of RFC 4750 for more details.

This version published as part of RFC 4750"

REVISION "199501201225Z" -- Fri Jan 20 12:25:50 PST 1995

DESCRIPTION

"The initial SMIv2 revision of this MIB module, published
in RFC 1850."

::= { ospf 16 }

-- Trap Support Objects

-- The following are support objects for the OSPF traps.

ospfTrapControl OBJECT IDENTIFIER ::= { ospfTrap 1 }
ospfTraps OBJECT IDENTIFIER ::= { ospfTrap 2 }

ospfSetTrap OBJECT-TYPE

SYNTAX OCTET STRING (SIZE(4))
MAX-ACCESS read-write

STATUS current

DESCRIPTION

"A 4-octet string serving as a bit map for
the trap events defined by the OSPF traps. This
object is used to enable and disable specific
OSPF traps where a 1 in the bit field
represents enabled. The right-most bit (least
significant) represents trap 0.

This object is persistent and when written

```

the entity SHOULD save the change to non-volatile
storage."
 ::= { ospfTrapControl 1 }

ospfConfigErrorType OBJECT-TYPE
SYNTAX      INTEGER {
                badVersion (1),
                areaMismatch (2),
                unknownNbmaNbr (3), -- Router is DR eligible
                unknownVirtualNbr (4),
                authTypeMismatch(5),
                authFailure (6),
                netMaskMismatch (7),
                helloIntervalMismatch (8),
                deadIntervalMismatch (9),
                optionMismatch (10),
                mtuMismatch (11),
                duplicateRouterId (12),
                noError (13) }
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "Potential types of configuration conflicts.
     Used by the ospfConfigError and
     ospfConfigVirtError traps. When the last value
     of a trap using this object is needed, but no
     traps of that type have been sent, this value
     pertaining to this object should be returned as
     noError."
 ::= { ospfTrapControl 2 }

ospfPacketType OBJECT-TYPE
SYNTAX      INTEGER {
                hello (1),
                dbDescript (2),
                lsReq (3),
                lsUpdate (4),
                lsAck (5),
                nullPacket (6) }
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "OSPF packet types. When the last value of a trap
     using this object is needed, but no traps of
     that type have been sent, this value pertaining
     to this object should be returned as nullPacket."
 ::= { ospfTrapControl 3 }

```

```

ospfPacketSrc OBJECT-TYPE
  SYNTAX      IpAddress
  MAX-ACCESS  read-only
  STATUS      current
  DESCRIPTION
    "The IP address of an inbound packet that cannot
     be identified by a neighbor instance. When
     the last value of a trap using this object is
     needed, but no traps of that type have been sent,
     this value pertaining to this object should
     be returned as 0.0.0.0."
 ::= { ospfTrapControl 4 }

-- Traps

ospfVirtIfStateChange NOTIFICATION-TYPE
  OBJECTS { ospfRouterId, -- The originator of the trap
            ospfVirtIfAreaId,
            ospfVirtIfNeighbor,
            ospfVirtIfState -- The new state
          }
  STATUS      current
  DESCRIPTION
    "An ospfvirtIfStateChange trap signifies that there
     has been a change in the state of an OSPF virtual
     interface.

    This trap should be generated when the interface
    state regresses (e.g., goes from Point-to-Point to Down)
    or progresses to a terminal state
    (i.e., Point-to-Point)."
 ::= { ospfTraps 1 }

ospfNbrStateChange NOTIFICATION-TYPE
  OBJECTS { ospfRouterId, -- The originator of the trap
            ospfNbrIpAddr,
            ospfNbrAddressLessIndex,
            ospfNbrRtrId,
            ospfNbrState -- The new state
          }
  STATUS      current
  DESCRIPTION
    "An ospfnbrStateChange trap signifies that
     there has been a change in the state of a
     non-virtual OSPF neighbor. This trap should be
     generated when the neighbor state regresses
     (e.g., goes from Attempt or Full to 1-Way or
     Down) or progresses to a terminal state (e.g.,

```

2-Way or Full). When an neighbor transitions from or to Full on non-broadcast multi-access and broadcast networks, the trap should be generated by the designated router. A designated router transitioning to Down will be noted by ospfIfStateChange."

::= { ospfTraps 2 }

ospfVirtNbrStateChange NOTIFICATION-TYPE
OBJECTS { ospfRouterId, -- The originator of the trap
 ospfVirtNbrArea,
 ospfVirtNbrRtrId,
 ospfVirtNbrState -- The new state
 }
STATUS current
DESCRIPTION
"An ospfVirtNbrStateChange trap signifies that there has been a change in the state of an OSPF virtual neighbor. This trap should be generated when the neighbor state regresses (e.g., goes from Attempt or Full to 1-Way or Down) or progresses to a terminal state (e.g., Full)."
 ::= { ospfTraps 3 }

ospfIfConfigError NOTIFICATION-TYPE
OBJECTS { ospfRouterId, -- The originator of the trap
 ospfIfIpAddress,
 ospfAddressLessIf,
 ospfPacketSrc, -- The source IP address
 ospfConfigErrorType, -- Type of error
 ospfPacketType
 }
STATUS current
DESCRIPTION
"An ospfIfConfigError trap signifies that a packet has been received on a non-virtual interface from a router whose configuration parameters conflict with this router's configuration parameters. Note that the event optionMismatch should cause a trap only if it prevents an adjacency from forming."
 ::= { ospfTraps 4 }

ospfVirtIfConfigError NOTIFICATION-TYPE
OBJECTS { ospfRouterId, -- The originator of the trap
 ospfVirtIfAreaId,
 ospfVirtIfNeighbor,
 ospfConfigErrorType, -- Type of error

```
    ospfPacketType
}
STATUS      current
DESCRIPTION
  "An ospfvirtIfConfigError trap signifies that a
  packet has been received on a virtual interface
  from a router whose configuration parameters
  conflict with this router's configuration
  parameters. Note that the event optionMismatch
  should cause a trap only if it prevents an
  adjacency from forming."
 ::= { ospfTraps 5 }

ospfIfAuthFailure NOTIFICATION-TYPE
  OBJECTS { ospfRouterId, -- The originator of the trap
            ospfIfIpAddress,
            ospfAddressLessIf,
            ospfPacketSrc, -- The source IP address
            ospfConfigErrorType, -- authTypeMismatch or
                                  -- authFailure
            ospfPacketType
          }
  STATUS      current
  DESCRIPTION
  "An ospfIfAuthFailure trap signifies that a
  packet has been received on a non-virtual
  interface from a router whose authentication key
  or authentication type conflicts with this
  router's authentication key or authentication
  type."
 ::= { ospfTraps 6 }

ospfVirtIfAuthFailure NOTIFICATION-TYPE
  OBJECTS { ospfRouterId, -- The originator of the trap
            ospfVirtIfAreaId,
            ospfVirtIfNeighbor,
            ospfConfigErrorType, -- authTypeMismatch or
                                  -- authFailure
            ospfPacketType
          }
  STATUS      current
  DESCRIPTION
  "An ospfVirtIfAuthFailure trap signifies that a
  packet has been received on a virtual interface
  from a router whose authentication key or
  authentication type conflicts with this router's
  authentication key or authentication type."
```

```
 ::= { ospfTraps 7 }

ospfIfRxBadPacket NOTIFICATION-TYPE
OBJECTS { ospfRouterId, -- The originator of the trap
          ospfIfIpAddress,
          ospfAddressLessIf,
          ospfPacketSrc, -- The source IP address
          ospfPacketType
        }
STATUS      current
DESCRIPTION
  "An ospfIfRxBadPacket trap signifies that an OSPF
   packet has been received on a non-virtual
   interface that cannot be parsed."
 ::= { ospfTraps 8 }

ospfVirtIfRxBadPacket NOTIFICATION-TYPE
OBJECTS { ospfRouterId, -- The originator of the trap
          ospfVirtIfAreaId,
          ospfVirtIfNeighbor,
          ospfPacketType
        }
STATUS      current
DESCRIPTION
  "An ospfVirtIfRxBadPacket trap signifies that an OSPF
   packet has been received on a virtual interface
   that cannot be parsed."
 ::= { ospfTraps 9 }

ospfTxRetransmit NOTIFICATION-TYPE
OBJECTS { ospfRouterId, -- The originator of the trap
          ospfIfIpAddress,
          ospfAddressLessIf,
          ospfNbrRtrId, -- Destination
          ospfPacketType,
          ospfLsdbType,
          ospfLsdbLsid,
          ospfLsdbRouterId
        }
STATUS      current
DESCRIPTION
  "An ospfTxRetransmit trap signifies than an
   OSPF packet has been retransmitted on a
   non-virtual interface. All packets that may be
   retransmitted are associated with an LSDB entry.
   The LS type, LS ID, and Router ID are used to
   identify the LSDB entry."
 ::= { ospfTraps 10 }
```

```
ospfvirtiftxretransmit NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
              ospfvirtIfAreaId,
              ospfvirtIfNeighbor,
              ospfPacketType,
              ospfLsdbType,
              ospfLsdbLsid,
              ospfLsdbRouterId
            }
    STATUS      current
    DESCRIPTION
      "An ospfvirtiftxretransmit trap signifies than an OSPF packet has been retransmitted on a virtual interface. All packets that may be retransmitted are associated with an LSDB entry. The LS type, LS ID, and Router ID are used to identify the LSDB entry."
    ::= { ospfTraps 11 }

ospforiginatelsa NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
              ospfLsdbAreaId, -- 0.0.0.0 for AS Externals
              ospfLsdbType,
              ospfLsdbLsid,
              ospfLsdbRouterId
            }
    STATUS      current
    DESCRIPTION
      "An ospforiginatelsa trap signifies that a new LSA has been originated by this router. This trap should not be invoked for simple refreshes of LSAs (which happens every 30 minutes), but instead will only be invoked when an LSA is (re)originated due to a topology change. Additionally, this trap does not include LSAs that are being flushed because they have reached MaxAge."
    ::= { ospfTraps 12 }

ospfmaxagelsa NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
              ospfLsdbAreaId, -- 0.0.0.0 for AS Externals
              ospfLsdbType,
              ospfLsdbLsid,
              ospfLsdbRouterId
            }
    STATUS      current
    DESCRIPTION
```

```
"An ospfMaxAgeLsa trap signifies that one of
the LSAs in the router's link state database has
aged to MaxAge."
 ::= { ospfTraps 13 }

ospfLsdbOverflow NOTIFICATION-TYPE
 OBJECTS { ospfRouterId, -- The originator of the trap
           ospfExtLsdbLimit
           }
STATUS      current
DESCRIPTION
 "An ospfLsdbOverflow trap signifies that the
 number of LSAs in the router's link state
 database has exceeded ospfExtLsdbLimit."
 ::= { ospfTraps 14 }

ospfLsdbApproachingOverflow NOTIFICATION-TYPE
 OBJECTS { ospfRouterId, -- The originator of the trap
           ospfExtLsdbLimit
           }
STATUS      current
DESCRIPTION
 "An ospfLsdbApproachingOverflow trap signifies
 that the number of LSAs in the router's
 link state database has exceeded ninety percent of
 ospfExtLsdbLimit."
 ::= { ospfTraps 15 }

ospfIfStateChange NOTIFICATION-TYPE
 OBJECTS { ospfRouterId, -- The originator of the trap
           ospfIfIpAddress,
           ospfAddressLessIf,
           ospfIfState -- The new state
           }
STATUS      current
DESCRIPTION
 "An ospfIfStateChange trap signifies that there
 has been a change in the state of a non-virtual
 OSPF interface. This trap should be generated
 when the interface state regresses (e.g., goes
 from Dr to Down) or progresses to a terminal
 state (i.e., Point-to-Point, DR Other, Dr, or
 Backup)."
 ::= { ospfTraps 16 }

ospfNssaTranslatorStatusChange NOTIFICATION-TYPE
 OBJECTS { ospfRouterId, -- The originator of the trap
```

```

    ospfAreaId,
    ospfAreaNssaTranslatorState -- The current translation
                                  -- status
}
STATUS      current
DESCRIPTION
  "An ospfNssaTranslatorStatusChange trap indicates that
   there has been a change in the router's ability to
   translate OSPF type-7 LSAs into OSPF type-5 LSAs.
   This trap should be generated when the translator
   status transitions from or to any defined status on
   a per-area basis."
 ::= { ospfTraps 17 }

ospfRestartStatusChange NOTIFICATION-TYPE
  OBJECTS { ospfRouterId, -- The originator of the trap
            ospfRestartStatus,
            ospfRestartInterval,
            ospfRestartExitReason
          }
STATUS      current
DESCRIPTION
  "An ospfRestartStatusChange trap signifies that
   there has been a change in the graceful restart
   state for the router. This trap should be
   generated when the router restart status
   changes."
 ::= { ospfTraps 18 }

ospfNbrRestartHelperStatusChange NOTIFICATION-TYPE
  OBJECTS { ospfRouterId, -- The originator of the trap
            ospfNbrIpAddr,
            ospfNbrAddressLessIndex,
            ospfNbrRtrId,
            ospfNbrRestartHelperStatus,
            ospfNbrRestartHelperAge,
            ospfNbrRestartHelperExitReason
          }
STATUS      current
DESCRIPTION
  "An ospfNbrRestartHelperStatusChange trap signifies that
   there has been a change in the graceful restart
   helper state for the neighbor. This trap should be
   generated when the neighbor restart helper status
   transitions for a neighbor."
 ::= { ospfTraps 19 }

ospfVirtNbrRestartHelperStatusChange NOTIFICATION-TYPE

```

```

OBJECTS { ospfRouterId, -- The originator of the trap
          ospfVirtNbrArea,
          ospfVirtNbrRtrId,
          ospfVirtNbrRestartHelperStatus,
          ospfVirtNbrRestartHelperAge,
          ospfVirtNbrRestartHelperExitReason
        }
STATUS      current
DESCRIPTION
  "An ospfVirtNbrRestartHelperStatusChange trap signifies
   that there has been a change in the graceful restart
   helper state for the virtual neighbor. This trap should
   be generated when the virtual neighbor restart helper
   status transitions for a virtual neighbor."
 ::= { ospfTraps 20 }

-- conformance information

ospfTrapConformance OBJECT IDENTIFIER ::= { ospfTrap 3 }
ospfTrapGroups      OBJECT IDENTIFIER ::= { ospfTrapConformance 1 }
ospfTrapCompliances OBJECT IDENTIFIER ::= { ospfTrapConformance 2 }

-- compliance statements

ospfTrapCompliance MODULE-COMPLIANCE
  STATUS      obsolete
  DESCRIPTION
    "The compliance statement."
  MODULE      -- this module
  MANDATORY-GROUPS { ospfTrapControlGroup }

  GROUP      ospfTrapControlGroup
  DESCRIPTION
    "This group is optional but recommended for all
     OSPF systems."
 ::= { ospfTrapCompliances 1 }

ospfTrapCompliance2 MODULE-COMPLIANCE
  STATUS      current
  DESCRIPTION
    "The compliance statement."
  MODULE      -- this module
  MANDATORY-GROUPS { ospfTrapControlGroup, ospfTrapEventGroup }
  OBJECT      ospfConfigErrorType
  MIN-ACCESS  accessible-for-notify
  DESCRIPTION
    "This object is only required to be supplied within
     notifications."

```

```
OBJECT      ospfPacketType
MIN-ACCESS  accessible-for-notify
DESCRIPTION
  "This object is only required to be supplied within
   notifications."
OBJECT      ospfPacketSrc
MIN-ACCESS  accessible-for-notify
DESCRIPTION
  "This object is only required to be supplied within
   notifications."
 ::= { ospfTrapCompliances 2 }

-- units of conformance

ospfTrapControlGroup    OBJECT-GROUP
  OBJECTS { ospfSetTrap,
            ospfConfigErrorType,
            ospfPacketType,
            ospfPacketSrc }
  STATUS    current
  DESCRIPTION
    "These objects are required to control traps
     from OSPF systems."
 ::= { ospfTrapGroups 1 }

ospfTrapEventGroup       NOTIFICATION-GROUP
  NOTIFICATIONS {
    ospfvirtIfStateChange,
    ospfnbrStateChange,
    ospfvirtNbrStateChange,
    ospfIfConfigError,
    ospfvirtIfConfigError,
    ospfIfAuthFailure,
    ospfvirtIfAuthFailure,
    ospfIfRxBadPacket,
    ospfvirtIfRxBadPacket,
    ospfTxRetransmit,
    ospfvirtIfTxRetransmit,
    ospfOriginateLsa,
    ospfMaxAgeLsa,
    ospfLsdbOverflow,
    ospfLsdbApproachingOverflow,
    ospfIfStateChange,
    ospfnssaTranslatorStatusChange,
    ospfRestartStatusChange,
    ospfnbrRestartHelperStatusChange,
    ospfvirtNbrRestartHelperStatusChange
  }
```

```
STATUS      current
DESCRIPTION
  "A grouping of OSPF trap events, as specified
   in NOTIFICATION-TYPE constructs."
 ::= { ospfTrapGroups 2 }

END
```

6. Security Considerations

There are a number of management objects defined in this MIB that have a MAX-ACCESS clause of read-write and/or read-create. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations.

It is recommended that attention be specifically given to implementing the MAX-ACCESS clause in a number of objects, including ospfIfAuthKey, ospfIfAuthType, ospfVirtIfAuthKey, and ospfVirtIfAuthType in scenarios that DO NOT use SNMPv3 strong security (i.e., authentication and encryption). Extreme caution must be used to minimize the risk of cascading security vulnerabilities when SNMPv3 strong security is not used. When SNMPv3 strong security is not used, these objects should have access of read-only, not read-create.

SNMPv1 by itself is not a secure environment. Even if the network itself is secure (for example by using IPsec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB.

It is recommended that the implementers consider the security features as provided by the SNMPv3 framework. Specifically, the use of the User-based Security Model RFC 3414 [RFC3414] and the View-based Access Control Model RFC 3415 [RFC3415] is recommended.

It is then a customer/user responsibility to ensure that the SNMP entity giving access to an instance of this MIB, is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

7. IANA Considerations

The MIB module in this document uses the following IANA-assigned OBJECT IDENTIFIER values recorded in the SMI Numbers registry:

Descriptor	OBJECT IDENTIFIER value
ospf	{ mib-2 14 }

8. Acknowledgements

This document was produced by the OSPF Working Group and is based on the MIB for OSPF version 2 by Rob Coltun and Fred Baker [RFC1850]. The editors would like to acknowledge John Moy, Rob Coltun, Randall Atkinson, David T. Perkins, Ken Chapman, Brian Field, Acee Lindem, Vishwas Manral, Roy Jose, Don Goodspeed, Vivek Dubey, Keith McCloghrie, Bill Fenner, and Dan Romascanu for their constructive comments.

9. References

9.1. Normative References

- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [RFC2578] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Structure of Management Information Version 2 (SMIV2)", STD 58, RFC 2578, April 1999.
- [RFC2579] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Textual Conventions for SMIV2", STD 58, RFC 2579, April 1999.
- [RFC2580] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Conformance Statements for SMIV2", STD 58, RFC 2580, April 1999.

9.2 Informative References

- [RFC1224] Steinberg, L., "Techniques for managing asynchronously generated alerts", RFC 1224, May 1991.
- [RFC1704] Haller, N. and R. Atkinson, "On Internet Authentication", RFC 1704, October 1994.
- [RFC1765] Moy, J., "OSPF Database Overflow", RFC 1765, March 1995.

- [RFC1793] Moy, J., "Extending OSPF to Support Demand Circuits", RFC 1793, April 1995.
- [RFC1850] Baker, F. and R. Coltun, "OSPF Version 2 Management Information Base", RFC 1850, November 1995.
- [RFC2328] Moy, J., "OSPF Version 2", STD 54, RFC 2328, April 1998.
- [RFC2370] Coltun, R., "The OSPF Opaque LSA Option", RFC 2370, July 1998.
- [RFC3101] Murphy, P., "The OSPF Not-So-Stubby Area (NSSA) Option", RFC 3101, January 2003.
- [RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction and Applicability Statements for Internet-Standard Management Framework", RFC 3410, December 2002.
- [RFC3414] Blumenthal, U. and B. Wijnen, "User-based Security Model (USM) for version 3 of the Simple Network Management Protocol (SNMPv3)", STD 62, RFC 3414, December 2002.
- [RFC3415] Wijnen, B., Presuhn, R., and K. McCloghrie, "View-based Access Control Model (VACM) for the Simple Network Management Protocol (SNMP)", STD 62, RFC 3415, December 2002.
- [RFC3584] Frye, R., Levi, D., Routhier, S., and B. Wijnen, "Coexistence between Version 1, Version 2, and Version 3 of the Internet-standard Network Management Framework", BCP 74, RFC 3584, August 2003.
- [RFC3623] Moy, J., Pillay-Esnault, P., and A. Lindem, "Graceful OSPF Restart", RFC 3623, November 2003.
- [RFC791] Postel, J., "Internet Protocol", STD 5, RFC 791, September 1981.
- [RFC3411] Harrington, D., Presuhn, R., and B. Wijnen, "An Architecture for Describing Simple Network Management Protocol (SNMP) Management Frameworks", STD 62, RFC 3411, December 2002.
- [RFC1583] Moy, J., "OSPF Version 2", RFC 1583, March 1994.

Appendix A. TOS Support

For backward compatibility with previous versions of the OSPF MIB specification, TOS-specific information has been retained in this document, though the TOS routing option has been deleted from OSPF [RFC2328].

Appendix B. Changes from RFC 1850

This section documents the differences between this memo and RFC 1850.

Appendix B.1. General Group Changes

Added object `ospfRFC1583Compatibility` to indicate support with "RFC 1583 Compatibility" [RFC1583]. This object has `DEFVAL` of "enabled".

Added object `ospfReferenceBandwidth` to allow configuration of a reference bandwidth for calculation of default interface metrics.

Added objects `ospfRestartSupport`, `ospfRestartInterval`, `ospfRestartAge`, `ospfRestartStrictLsaChecking`, and `ospfRestartExitReason` to support graceful restart.

Added objects `ospfStubRouterSupport` and `ospfStubRouteAdvertisement` to support stub routers.

Added object `ospfDiscontinuityTime` in order for a management entity to detect counter discontinuity events.

Appendix B.2. OSPF NSSA Enhancement Support

Added new objects to `OspfAreaTable` including the following:

- `ospfAreaNssaTranslatorRole` to indicate the configured NSSA translation role.
- `ospfAreaNssaTranslatorState` to indicate the current NSSA translation role.
- `ospfAreaNssaTranslatorStabilityInterval` to indicate time to continue to perform at current translation status.
- `ospfAreaNssaTranslatorEvents` to indicate the number of times OSPF translation state has changed.

Added new object `ospfAreaAggregateExtRouteTag` to `ospfAreaAggregateTable`.

Added new object `ospfNssaTranslatorStatusChange` to `ospfTraps` in OSPF-TRAP-MIB DEFINITIONS.

Added `ospfAreaId` to IMPORTS in OSPF-TRAP-MIB DEFINITIONS to support `ospfNssaTranslatorStatusChange`.

Added `ospfAreaExtNssaTranslatorStatus` to IMPORTS in OSPF-TRAP-MIB DEFINITIONS to support `ospfNssaTranslatorStatusChange`.

Modified the DESCRIPTION clause of the `ospfAreaSummary` object in the `ospfAreaTable` to indicate support for NSSA.

Modified the DESCRIPTION clause of the `ospfImportAsExtern` object in the `ospfAreaTable` for clarity.

Appendix B.3. Opaque LSA Support

Added object `ospfOpaqueLsaSupport` to `ospfGeneralGroup` to indicate support of OSPF Opaque LSAs.

Created `ospfLocalLsdbTable`, for link-local (type-9) LSA support. This table is indexed by the following:

- `ospflocalLsdbIpAddress`
- `ospfLocalLsdbAddressLessIf`
- `ospfLocalLsdbType`
- `ospfLocalLsdbLsid`
- `ospfLocalLsdbRouterId`

`ospfLocalLsdbTable` contains the following (columnar) objects:

- `ospfLocalLsdbSequence`, to indicate LSA instance
- `ospfLocalLsdbAge`
- `ospfLocalLsdbChecksum`
- `ospfLocalLsdbAdvertisement`, containing the entire LSA

Created `ospfVirLocalLsdbTable`, for link-local (type-9) LSA support on virtual links. This table is indexed by the following:

- `ospfVirtLocalLsdbTransitArea`

-`ospfVirtLocalLsdbNeighbor`, to indicate the router ID of the virtual neighbor

-`ospfVirLocalLsdbType`

-`ospfVirLocalLsdbLsid`

-`ospfVirLocalLsdbRouterId`

`ospfVirLocalLsdbTable` contains the following (columnar) objects:

-`ospfVirLocalLsdbSequence`, to indicate LSA instance

-`ospfVirLocalLsdbAge`

-`ospfVirLocalLsdbChecksum`

-`ospfVirLocalLsdbAdvertisement`, containing the entire LSA

Added objects to `ospfIfTable` to support link-local (type-9) LSAs, including the following:

-`ospfIfLsaCount`

-`ospfIfLsaCksumSum`, to indicate the sum of the type-9 link state advertisement checksums on this interface

Added objects to `ospfVirIfTable`, to support link-local (type-9) LSAs on virtual links, including the following:

-`ospfVirIfLsaCount`

-`ospfVirIfLsaCksumSum`, to indicate the sum of the type-9 link state advertisement checksums on this link

To support area scope (type-10) LSAs, the enumeration `areaOpaqueLink` (10) was added to `ospfLsdbType` in the `ospfLsdbTable`.

Created `ospfAsLsdbTable`, for AS-scope LSA support. This table is indexed by the following:

-`ospfAsLsdbType`

-`ospfAsLsdbLsid`

-`ospfAsLsdbRouterId`

`ospfAsLsdbTable` contains the following (columnar) objects:

- ospfAsLsdbSequence, to indicate LSA instance
- ospfAsLsdbAge
- ospfAsLsdbChecksum
- ospfAsLsdbAdvertisement, containing the entire LSA

Appendix B.4. Graceful Restart Support

Added objects ospfRestartSupport, ospfRestartInterval, ospfRestartAge, ospfRestartStrictLsaChecking, and ospfRestartExitReason to general group.

Added objects ospfNbrRestartHelperStatus, ospfNbrRestartHelperAge, and ospfNbrRestartHelperExitReason to OspfNbrTable.

Added objects ospfVirtNbrRestartHelperStatus, ospfVirtNbrRestartHelperAge, and ospfVirtNbrRestartHelperExitReason to OspfVirtNbrTable.

Appendix B.5. OSPF Compliances

New compliance statements were added for new and for obsoleted conformance groups. These statements include the following:

- ospfCompliance2
- ospfComplianceObsolete

New conformance groups were created to support new objects added to the group. These groups include the following:

- ospfBasicGroup2
- ospfAreaGroup2
- ospfIfGroup2
- ospfVirtIfGroup2
- ospfNbrGroup2
- ospfVirtNbrGroup2
- ospfAreaAggregateGroup2

Added completely new conformance groups, including the following:

- `ospfLocalLsdbGroup`, which specifies support for link-local (type-9) LSAs
- `ospfVirtLocalLsdbGroup`, which specifies support for link-local (type-9) LSAs on virtual links
- `ospfObsoleteGroup`, for obsolete objects and SMI compatibility

Appendix B.6. OSPF Authentication and Security

As there has been significant concern in the community regarding cascading security vulnerabilities, the following changes have been incorporated:

- Modified the DESCRIPTION clause of `ospfIfAuthKey` due to security concerns and to increase clarity
- Modified the DESCRIPTION clause of `ospfVirtIfAuthKey` due to security concerns and to increase clarity
- Modified the DESCRIPTION clause of `ospfIfAuthType` due to security concerns and to increase clarity
- Modified the DESCRIPTION clause of `ospfVirtIfType` due to security concerns and to increase clarity
- Modified the OSPF MIB MODULE DESCRIPTION due to security concerns and to include a reference to the Security Considerations section in this document that will transcend compilation
- Modified the Security Considerations section to provide detail

Appendix B.7. OSPF Trap MIB

Added `ospfTrapEventGroup`.

Added importation of NOTIFICATION-GROUP.

Changed the STATUS of the `ospfTrapCompliance` MODULE-COMPLIANCE construct to obsolete.

Added `ospfTrapCompliance2` MODULE-COMPLIANCE construct, which replaces `ospfTrapCompliance`. `OspfTrapCompliance` includes an updated MANDATORY-GROUPS clause and new MIN-ACCESS specifications.

Added `mtuMismatch` enumeration to `ospfConfigErrorType` object in `ospfTrapControl` to imply MTU mismatch trap generation. in `ospfIfConfigError`.

Added noError enumeration to ospfConfigErrorType object for situations when traps are requested but none have been sent. Updated the DESCRIPTION clause accordingly.

Added nullPacket enumeration to ospfPacketType object for situations when traps are requested but none have been sent. Updated the DESCRIPTION clause accordingly.

Updated the DESCRIPTION clause of ospfPacketSrc for situations when traps are requested, but none have been sent.

Added NOTIFICATION-TYPE for ospfRestartStatusChange.

Added NOTIFICATION-TYPE for ospfNbrRestartHelperStatusChange.

Added NOTIFICATION-TYPE for ospfVirtNbrRestartHelperStatusChange.

Appendix B.8. Miscellaneous

Various sections have been moved or modified for clarity. Most of these changes are semantic in nature and include, but are not limited to the following:

- The OSPF overview section's format was revised. Unneeded information was removed. Removed information includes OSPF TOS default values.
- The trap overview section's format and working were revised. Unneeded information was removed.
- Modified the DESCRIPTION clause of "Status" "TEXTUAL-CONVENTION" for clarity.
- The Updates section was moved from the overview to its own section.
- Updated "REFERENCE" clauses in all objects, as needed.
- Modified the SEQUENCE of the OspfIfTable to reflect the true order of the objects in the table.
- Modified the DESCRIPTION clause of all row management objects for clarity.

Added ospfHostCfgAreaID to object to Host table with read-create access. Deprecated ospfHostAreaID.

Added importation of InterfaceIndexOrZero from IF-MIB. This TEXTUAL-CONVENTION will replace the InterfaceIndex TEXTUAL-CONVENTION.

Changed the SYNTAX clause of ospfNbrAddressLessIndex to use the semantically identical InterfaceIndexOrZero TEXTUAL-CONVENTION, as permitted by the SMI.

Changed the STATUS clause of the TEXTUAL-CONVENTION InterfaceIndex to obsolete and modified the DESCRIPTION accordingly.

Changed the SYNTAX clause of ospfAddressLessIf to use the semantically identical InterfaceIndexOrZero TEXTUAL-CONVENTION, as permitted by the SMI.

Changed the SYNTAX clause of ospfIfMetricAddressLessIf to use the semantically identical InterfaceIndexOrZero TEXTUAL-CONVENTION, as permitted by the SMI.

Changed importation of mib-2 from RFC1213-MIB to SNMPv2-SMI

Added Intellectual Property Rights section.

Updated REVISION DESCRIPTION clauses with description of major MIB modifications.

Moved all relevant MIB comments to objects' DESCRIPTION clauses.

Added reasoning for object deprecation.

Added persistence information for read-write, read-create objects.

Described conditions when columns can be modified in RowStatus managed rows as required by RFC 2579.

Defined OspfAuthenticationType TC and modified authentication type objects to use the new type.

Made index objects of new tables not accessible.

Added the UNITS clause to several objects.

Added ospfIfDesignatedRouterId and ospfIfBackupDesignatedRouterId to the OspfIfEntry.

Added the area LSA counter table.

Added IANA Considerations section.

Authors' Addresses

Dan Joyal (Editor)
Nortel, Inc.
600 Technology Park Drive
Billerica, MA 01821
USA

EMail: djoyal@nortel.com

Piotr Galecki (Editor)
Airvana, Inc.
19 Alpha Road
Chelmsford, MA 01824
USA

EMail: pgalecki@airvana.com

Spencer Giacalone (Editor)
CSFB
Eleven Madison Ave
New York, NY 10010-3629
USA

EMail: spencer.giacalone@gmail.com

Fred Baker
Cisco Systems
1121 Via Del Rey
Santa Barbara, California 93117
USA

EMail: fred@cisco.com

Rob Coltun
Touch Acoustra
3204 Brooklawn Terrace
Chevy Chase, MD 20815
USA

EMail: undisclosed

Full Copyright Statement

Copyright (C) The IETF Trust (2006).

This document is subject to the rights, licenses and restrictions contained in BCP 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY, THE IETF TRUST, AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the procedures with respect to rights in RFC documents can be found in BCP 78 and BCP 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at <http://www.ietf.org/ipr>.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.

